



novaPDF SDK

Paperless office solutions

novaPDF SDK User Manual

Copyright © 2008 Softland

novaPDF SDK User Manual

for novaPDF SDK version 5

by Softland

This documentation contains proprietary information of Softland. All rights reserved. No part of this documentation shall be reproduced, stored in a retrieval system or transmitted by any means, electronic, mechanical, photocopying, recoding, or otherwise, without permission from Softland. No patent liability is assumed with respect to the use of the information contained herein.

The information in this document is subject to change without notice. Although every precaution has been taken in the preparation of this book, Softland assumes no responsibility for errors and omissions. Nor is any liability assumed for damages resulting from the information contained herein.

Windows ® is a registered trademark of the Microsoft Corporation. All other products or company names in this document are used for identification purposes only, and may be trademarks of their respective owners.

Table of Contents

Part I Introduction **7**

Part II novaPDF SDK **9**

- 1 Overview** **9**
 - Installation9
 - System requirements9
 - Components9
 - Network use 10
 - novaPDF Printer Editions 11
- 2 Integration**..... **11**
 - How to integrate 11
 - How to make the release build 12
 - How to distribute 12
 - Silent Installer 12
 - Language codes 14
- 3 novaPDF COM**..... **15**
 - How to register COM 15
 - How to use the COM 15
 - How to set printer options 16
 - Private and public profiles 17
 - How to register for messages 17
 - How to use events 18
 - Reference** 18
 - Registry keys 18
 - Windows messages..... 25
 - What is INovaPdfOptions..... 26
 - INovaPdfOptions..... 28
 - Initialize 28
 - Initialize2 29
 - InitializeSilent 29
 - InitializeSilent2 30
 - GetOptionString 30
 - GetOptionString2 31
 - GetOptionEncString 32
 - GetOptionEncString2 32
 - SetOptionString 33
 - SetOptionString2 34
 - SetOptionEncString 34
 - SetOptionEncString2 35
 - GetOptionLong 36
 - GetOptionLong2 36
 - SetOptionLong 37
 - SetOptionLong2 37
 - AddProfile 38
 - AddProfile2 38
 - CopyProfile 39

CopyProfile2	39
RenameProfile	40
RenameProfile2	40
DeleteProfile	41
DeleteProfile2	41
GetFirstProfile	41
GetFirstProfile2	42
GetNextProfile	42
GetNextProfile2	43
GetActiveProfile	43
GetActiveProfile2	44
SetActiveProfile	44
SetActiveProfile2	44
AddPredefinedForm	45
AddPredefinedForm2	45
GetPredefinedForm	46
GetPredefinedForm2	47
RemovePredefinedForm	47
RemovePredefinedForm2	48
SetFormVisible	48
SetFormVisible2	49
GetFirstForm	49
GetFirstForm2	50
GetNextForm	51
GetNextForm2	51
SetDefaultPrinter	52
RestoreDefaultPrinter	52
RegisterEventWindow	53
UnRegisterEventWindow	53
RegisterNovaEvent	53
RegisterNovaEvent2	53
WaitForNovaEvent	54
InitializeOLEUsage	54
LicenseOLEServer	54
LicenseShellExecuteFile	54
LicenseApplication	55
AddBookmarkDefinition	55
AddBookmarkDefinition2	56
ModifyBookmarkDefinition	57
ModifyBookmarkDefinition2	59
DeleteBookmarkDefinition	60
DeleteBookmarkDefinition2	60
EnableBookmarkDefinition	61
EnableBookmarkDefinition2	62
GetBookmarkDefinition	62
GetBookmarkDefinition2	63
GetBookmarkHeaderCount	64
GetBookmarkHeaderCount2	65
GetBookmarkDefinitionCount	65
GetBookmarkDefinitionCount2	66
AddWatermarkImage	66
AddWatermarkImage2	68
ModifyWatermarkImage	70
ModifyWatermarkImage2	72

DeleteWatermarkImage	74
DeleteWatermarkImage2	74
EnableWatermarkImage	74
EnableWatermarkImage2	75
GetWatermarkImage	75
GetWatermarkImage2	77
GetWatermarkImageCount	79
GetWatermarkImageCount2	79
AddWatermarkText	80
AddWatermarkText2	82
ModifyWatermarkText	83
ModifyWatermarkText2	85
DeleteWatermarkText	87
DeleteWatermarkText2	87
EnableWatermarkText	88
EnableWatermarkText2	88
GetWatermarkText	89
GetWatermarkText2	91
GetWatermarkTextCount	92
GetWatermarkTextCount2	93
GetPDFFileName	93
4 Samples.....	94
What sample to choose	94
Access	95
PDF Reports	95
Delphi	96
VCL Converter	96
Hello World Delphi	100
Word OLE Delphi.....	102
C#	104
Hello World CSharp	104
CSharp Converter.....	106
Word OLE CSharp.....	108
C++	110
Hello World	110
Hello World (network).....	113
MFC Converter	115
MFC Scribble	118
VB	120
Hello World VB	120
VB Converter	121
Word OLE VB	124
VBNet	125
Hello World VBNet.....	125
VBNet Converter	126
Word OLE VBNet.....	128
5 Licensing and Registration.....	129
 Index	 131

Introduction

Part



1 Introduction

novaPDF SDK is a PDF software development kit that programmers and software developers can use to add the ability to create PDF files in their own applications.

Why use novaPDF SDK?

With novaPDF SDK you can integrate novaPDF's printing capabilities in your applications. You just have to send your document to novaPDF Printer, as you would print the document to a normal printer, and a PDF file will be generated instead of printing on paper.

You can choose a default folder and file name for generated PDF files, or you can set them for each print job. You can also choose different options for the output PDF file, including image compression, font embedding, PDF security and document metadata.

novaPDF SDK package


novaPDF SDK includes:

- novaPDF Printer Professional
- a COM interface for customizing novaPDF Printer options, named `INovaPdfOptions`. Any option that can be configured in the novaPDF Printer Printing Preferences dialog is also configurable through the COM interface, including profiles management.
- a Silent Installer for novaPDF Printer Professional that can be distributed with your software. You can include this silent installer in your installation program and novaPDF Printer will be installed with your customized options, without any user interaction.
- several samples of how to use novaPDF SDK

See Components for the complete list.

novaPDF SDK

Part



2 novaPDF SDK

2.1 Overview

2.1.1 Installation

Install

To install novaPDF SDK on a computer you need to have administrative rights because novaPDF SDK installer also installs novaPDF Printer Professional on your computer.

The installation process does not take much time. All you need to do is to follow the instructions of the "Setup - novaPDF SDK" wizard. There is no need to reboot at the end of the setup; you can run the program right after it is installed on your machine.

If you have already installed an older version of novaPDF SDK, the installer calls first the uninstaller for the installed version and after that installs the new version. After installing the new version you might be requested to restart.

Uninstall

Go to the novaPDF SDK application group (from Windows' "Start" menu and click "Uninstall novaPDF SDK").

You can also uninstall the application using the "Add/Remove Programs" icon from the "Control Panel".

2.1.2 System requirements

To install novaPDF SDK you need Windows 2000/XP/XP x64/2003 Server/2003 Server x64/Vista/Vista x64 and approximately 16 megabytes of free disk space.

2.1.3 Components

novaPDF SDK installs by default in the "C:\Program Files\Softland\novaPDF SDK" folder, but you can change this path during the installation process. The installer will create the following folder structure:

Doc

- contains the help file and the license files

Include

- definition files for INovaPdfOptions interface
- definitions for Windows messages and Registry keys

Installer

- novapin.exe - novaPDF Printer Pro Silent Installer. You may use this installer when deploying your application.

Lib

- novapi5.dll - INovaPdfOptions binary file that is installed by all editions of novaPDF Printer. There are two versions of the dll, one for i386 systems and one for x64 systems

Samples

Contains several samples of how to use INovaPdfOptions:

- Access PDF Reports - make a report on an Access database and convert it to PDF
- C++ Hello World - a console application that prints one page to the novaPDF Printer
- C++ Hello World (network) - the same as Hello World sample, but it can be run from any computer in the network, thought the novaPDF Printer is installed on one single computer

- C++ MFC Scribble - the standard MFC Scribble sample extended with generate PDF files
- C++ MFC Converter - a MFC dialogs sample that converts an existing file to PDF using different profiles on novaPDF Printer
- C# Hello World CSharp - a simple Windows console application that prints one page to the novaPDF Printer.
- C# CSharp Converter - converts an existing file to PDF using different profiles on novaPDF Printer
- C# Word OLE CSharp - converts a MS Word Document to PDF using Word automation
- Delphi Hello World Delphi - a Delphi application that prints using the Printer object
- Delphi VCL Converter- a Delphi application that converts an existing file to PDF using different profiles on novaPDF Printer
- Delphi Word OLE Delphi - converts a MS Word Document to PDF using Word automation
- VB Hello World VB - a VB application that prints using Printer object
- VB VB Converter - a VB application that converts an existing file to PDF using different profiles on novaPDF Printer
- VB Word OLE VB - converts a MS Word Document to PDF using Word automation
- VBNet Hello World VBNet - a VBNet console application that prints one page to the novaPDF Printer.
- VBNet VBNet Converter - a VBNet application that converts an existing file to PDF using different profiles on novaPDF Printer
- VBNet Word OLE VBNet - converts a MS Word Document to PDF using Word automation

Bin

- sample executables for DotNet, Win32 and Win64

2.1.4 Network use

novaPDF Printer network auto-install

novaPDF Printer Server Edition can be installed on one computer and can be used by any computer in the network, without having to install it on each computer. This is to ease the work of network administrators both at installation time and future upgrades.

novaPDF Printer Server driver supports Point and Print technology. This means that you can install the printer on one computer on the network, share it, and you can connect to it from any other computer. The system copies the necessary files for the driver, without any user interaction. On the server there are installed both i386 and x64 drivers and you can connect from the network with any i386 or x64 computers.

For more details on how the novaPDF Printer Server can be installed and licensed on the network see the novaPDF Printer help file.

How to use novaPDF SDK in a network

If you have a large network you can install novaPDF Printer Server and your application which integrates novaPDF SDK on a single computer and use it from any computer in the network. All you need to do in your software is to initialize the INovaPdfOptions interface with the correct printer name, including the name of the computer on which it is installed (like "\\server\novaPDF Server Pro v5").

When the application initiates the first print job to the printer server, the system copies the necessary printer driver files without any user interaction and the print job is completed on the printer server.

You can configure private or public profiles on the printer server. Public profiles will be copied on the client computers when you open the Printing Preferences dialog on client computers or when performing a print job to the printer server. Private profiles are saved and read from the local registry. See Private and public profiles for more details.

The COM has to be registered on every computer that uses it. But this can be done

programmatically, as you can see it in the Hello World (network) sample.

2.1.5 novaPDF Printer Editions

There are three licensing options for novaPDF Printer: Lite, Standard and Professional. All of them implement the basic functionalities of a PDF Printer: print from any Windows application, predefined page sizes, custom page sizes, page orientation, page margins, printing resolution, document scaling, PDF document information, automatically save and open PDF file, select user interface language, etc.

The Standard Edition has additional features, like: extended paper settings for zoom and margins, text and image compression, font embedding and sub-setting, user profiles.

The Professional Edition adds PDF security, PDF Links and Email to the features of Standard Edition.

If you only want to create simple PDF files, with no advanced options, you should choose the Lite edition. When printing to novaPDF Printer Lite, you can only choose the printing options (page size, resolution, etc.), fill the PDF document information (title, subject, etc.) or enter the name of the resulting PDF file.

If you want to have the possibility to choose from different levels of compression, to choose to embed font or font subsets then go for Standard Edition. If you want to apply PDF security for the resulting PDF files, if you want to detect PDF Links, or if you want to automatically send the PDF file by email, then you will need the Professional Edition.

You can also choose between a desktop edition or a Server edition. If you use novaPDF printer on only one computer, you should choose the desktop edition. But if you want to use novaPDF Printer as a shared network printer or in a Terminal Server environment, you should choose a Server edition. The Server edition adds features like license management and public profiles.

novaPDF SDK works with any of the three editions of novaPDF Printer. The silent installers included in the SDK is for novaPDF Pro and novaPDF Server Pro editions.

For more details about the features of each edition see novaPDF Printer documentation and help file.

2.2 Integration

2.2.1 How to integrate

You have to follow these steps for integrating novaPDF SDK in your application:

1. Install novaPDF SDK

When installing novaPDF SDK, there is also installed on your computer novaPDF Printer Professional. You will see a "novaPDF Pro v5" printer in your "Printers and Faxes" list.

2. Take a sample and test it.

See What sample to choose topic for directions how to choose the best sample for your situation.

3. Copy relevant code from the sample in your application.

Be sure you include all next steps from samples:

- start a print job and write to the printer device context (using functions like CreateDC, StartDoc, StartPage, TextOut,...). Or open a file and print it with other methods, like calling ShellExecute().
- customize novaPDF Printer settings using INovaPdfOptions COM interface (for instance set the output file name and folder, document info,...). If you do not wish to install and use the

COM interface, you can write these settings directly in registry. See Registry keys topic for a list of all registry keys.

- register Windows messages to receive the printing events (page finished, document finished, errors...)

4. Test how your application prints to novaPDF printer.

When you print to novaPDF printer, the generated PDF files have the "Created with novaPDF..." text written on the bottom of all pages. To remove this text please read the How to make the release build topic.

5. Install novaPDF Professional Server edition

If you want to install novaPDF printer as a shared network printer or if you want to install it on a Terminal Server, you have to install the Server edition instead of the Desktop edition. The installer is located in the novaPDF SDK installation folder, Installer \ novapsv.exe

2.2.2 How to make the release build

After you succeeded to integrate novaPDF SDK in your application (see How to integrate topic) you have to follow next steps:

1. Purchase a novaPDF license

If you want to remove the novaPDF texts from the generated PDF files, you have to register either novaPDF Printer or novaPDF SDK. See Purchasing and Registration for more details.

2. Register novaPDF

If you have a novaPDF Printer License, register the printer from the Printing Preferences, About page. If you have an application license for novaPDF SDK, pass the registration name and key to the Initialize function of INovaPdfOptions.

3. Print without novaPDF notice

Now if you perform a print to the registered novaPDF Printer, the generated PDF file should not have any novaPDF notice.

2.2.3 How to distribute

Install novaPDF Printer on each computer

If you install your application on each customer computer, then you can include our Silent Installer in your application setup. You can customize the group name and the folder where novaPDF Printer will be installed. You can also customize the printer name and you can register the printer automatically using the silent installer command line parameters.

Install novaPDF Printer Server on one computer and share it as a network printer

If you have a network you can install novaPDF Printer Server on a single computer and share it as a network printer. You can run your application on any computer in the network and print to the shared printer. The advantage is when you upgrade novaPDF Printer to a new version, you only will have to upgrade on the printer server computer. See Network use for more details.

2.2.4 Silent Installer

You can integrate a silent installer for novaPDF Printer in the setup of your application. There are two installers in the Installer folder:

- **novapin.exe** - installs novaPDF Professional printer
- **novapsv.exe** - installs novaPDF Server Professional printer

You have to call the silent installer in your setup process.

Install novaPDF Printer

The silent installers have the following command line parameters:

/SILENT, /VERYSILENT

Instructs Setup to be silent or very silent. When Setup is silent the wizard and the background window are not displayed but the installation progress window is. When a setup is very silent this installation progress window is not displayed. Everything else is normal so for example error messages during installation are displayed

If a restart is necessary and the /NORESTART command isn't used (see below) and Setup is silent, it will display a Reboot now? message box. If it's very silent it will reboot without asking.

/SUPPRESSMSGBOXES

Instructs Setup to suppress message boxes. Only has an effect when combined with /SILENT and /VERYSILENT.

/NOCANCEL

Prevents the user from cancelling during the installation process, by disabling the Cancel button and ignoring clicks on the close button. Useful along with /SILENT or /VERYSILENT.

/NORESTART

Instructs Setup not to reboot even if it's necessary.

/RESTARTEXITCODE=exit code

Specifies the custom exit code that Setup is to return when a restart is needed. Useful along with /NORESTART'

/DIR="x:\dirname"

Overrides the default directory name displayed on the Select Destination Location wizard page. A fully qualified pathname must be specified.

/GROUP="folder name"

Overrides the default folder name displayed on the Select Start Menu Folder wizard page.

/LANG="language"

Specifies the language to use for the installation. When a valid /LANG parameter is used, the Select Language dialog will be suppressed.

/Languages="language1-language2-..."

Specifies the languages that will be installed. Use short language codes (like "en-it"). See the complete Language codes list.

/DefaultLang="language"

Specifies the default language. Use short language codes (like "en") or the "REGST" constant for "Use regional settings" option. See the complete Language codes list.

/PrinterName="printer name"

Name of the installed printer. By default the name is "novaPDF Pro v5"

/RegisterName="registration name"

novaPDF Printer registration name

/RegisterKey="license key"

novaPDF Printer Registration key (not the sdk application license key, but the printer license key)

/Default

Instructs setup to set the printer as default printer.

/NoInstallIfExists

Instructs setup to check if novaPDF Professional Desktop printer is already installed, and if it is, does not start the installation

Here is an example of how to call the silent installer:

```
novapin.exe /VERYSILENT /SUPPRESSMSGBOXES /NOCANCEL /NORESTART /PrinterName="novaPDF Professional Desktop 5"
```

Uninstall novaPDF Printer

When installing novaPDF Printer, there will be added a Start Menu folder for the novaPDF Printer. There will be also an menu item for the uninstaller.

If you installed with default directory name, the uninstaller is located at:

"C:\Program Files\Softland\novaPDF Printer Professional Desktop 5\unins000.exe".

The uninstaller has also some parameters for silent uninstall (they have the same meaning as for the installer, see above for details):

/SILENT

/VERYSILENT

/SUPPRESSMSGBOXES

/NORESTART

2.2.5 Language codes

Here are all available languages for novaPDF printer:

Language code	Language name
bg	Bulgarian
br	Portuguese (Brazilian)
cs	Czech
ct	Chinese Traditional
de	German
en	English
es	Spanish
fr	French
gr	Greek
hu	Hungarian
it	Italian
ja	Japanese
kr	Korean
nl	Dutch (Netherlands)
pl	Polish
pt	Portuguese
ro	Romanian
ru	Russian
sc	Simplified Chinese

si	Slovenian
sr	Serbian
sv	Swedish
uk	Ukrainian
vi	Vietnamese

2.3 novaPDF COM

2.3.1 How to register COM

novaPDF SDK includes a COM interface, `INovaPdfOptions`. The COM binary file is located in the `Lib` sub folder. The COM is first registered when installed with novaPDF SDK. If you want to register/unregister novaPDF COM manually, use the following commands from the command line:

Register

```
regsvr32.exe "C:\Program Files\Softland\novaPDF SDK 5\Lib\novapi5.dll"
```

or, for x64 systems:

```
regsvr32.exe "C:\Program Files\Softland\novaPDF SDK 5\Lib\x64\novapi5.dll"
```

Unregister

```
regsvr32.exe /u "C:\Program Files\Softland\novaPDF SDK 5\Lib\novapi5.dll"
```

or, for x64 systems:

```
regsvr32.exe /u "C:\Program Files\Softland\novaPDF SDK 5\Lib\x64\novapi5.dll"
```

You can also register the COM programmatically, from your application. See Hello World (network) sample for an example how to do it. This way you don't have to manually install your application on all computers on the network, you can install it on a central computer and access it from the other computers.

NovaPDF COM dll

- `novapi5.dll` - This is the distributable version of COM. You will need to register this COM when you have an "Application License"

2.3.2 How to use the COM

To use novaPDF COM in your application you need to follow next steps:

1. Create an instance of `INovaPdfOptions` interface

2. Call the `Initialize` method with the following parameters

- name of the printer (for example "novaPDF Pro v5", or when on the network "\\server name\novaPDF Server Pro v5")
- name of the registered user (can be empty when not registered)
- license key (can be empty when not registered)

3. Set novaPDF Printer options by calling `SetOptionString` or `SetOptionLong` methods.

You can also manage profiles with `AddProfile`, `CopyProfile`, `RenameProfile`, `DeleteProfile`, `GetFirstProfile`, `GetNextProfile`, `GetActiveProfile`, `SetActiveProfile` methods. A good sample for how to use this methods is the MFC Converter sample.

This step is optional. If you use the default options or if you already configured the desired options, you can skip it.

4. Register for novaPDF Printer Windows messages (`StartDoc`, `StartPage`, `EndPage`, `EndDoc`, `FileSent`, `Print Error`) using the `RegisterEventWindow` method. You also need to

implement message handlers for the registered messages. See MFC Scribble or MFC Converter samples.

This step is also optional. If you do not need to implement this event handlers you can skip it.

5. Start a print job. You can do it as follows:

- use Win32 API functions: OpenPrinter, DocumentProperties, CreateDC, StartDoc, StartPage,... See the Hello World sample.
- print a file using the ShellExecute function. For a sample see MFC Converter.
- use MFC document/view architecture. For more information look at the MFC Scribble sample.

6. Release the INovaPdfOptions instance.

2.3.3 How to set printer options

You can use INovaPdfOptions interface to read or set novaPDF Printer options.

INovaPDFOptions provides the following methods for this:

GetOptionString
SetOptionString
GetOptionLong
SetOptionLong
GetOptionEncString
SetOptionEncString
AddPredefinedForm
GetPredefinedForm
RemovePredefinedForm
SetFormVisible
GetFirstForm
GetNextForm
AddBookmarkDefinition
AddBookmarkDefinition2
ModifyBookmarkDefinition
ModifyBookmarkDefinition2
DeleteBookmarkDefinition
DeleteBookmarkDefinition2
EnableBookmarkDefinition
EnableBookmarkDefinition2
GetBookmarkDefinition
GetBookmarkDefinition2
GetBookmarkHeaderCount
GetBookmarkHeaderCount2
GetBookmarkDefinitionCount
GetBookmarkDefinitionCount2
AddWatermarkImage
AddWatermarkImage2
ModifyWatermarkImage
ModifyWatermarkImage2
DeleteWatermarkImage
DeleteWatermarkImage2
EnableWatermarkImage
EnableWatermarkImage2
GetWatermarkImage
GetWatermarkImage2
GetWatermarkImageCount
GetWatermarkImageCount2
AddWatermarkText
AddWatermarkText2

ModifyWatermarkText
ModifyWatermarkText2
DeleteWatermarkText
DeleteWatermarkText2
EnableWatermarkText
EnableWatermarkText2
GetWatermarkText
GetWatermarkText2
GetWatermarkTextCount
GetWatermarkTextCount2

The options are saved in the current active profile. See Private and public profiles topic for more details about profiles.

You have to make these settings before starting the print job.

The option names that you can use in the `GetOptionXXXX` and `SetOptionXXXX` functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: `novaOptions.h`, `novaOptions.pas`, `Globals.bas`.

2.3.4 Private and public profiles

Public profiles are visible from all client computers. You are only allowed to create public profiles on the printer server computer. When a client computer connects to the printer server, or when it opens the Printing Preferences dialog, the public profiles are copied from the printer server to the client computer.

You should use public profiles if you want to configure printing options that should be used by several computers in your network. For instance, you can configure a folder where all client computers will save the PDF files.

For public profiles, the options are saved in a file in printer drivers folder, on the server. You should write in public profiles only when you are using a Server edition and your application runs on the printer server computer. Public profiles files are automatically copied from the printer server computer to the client computers. On the client computers, the public profiles file resides in the Application Data folder of the user that connected to the printer.

Public profiles have a flag called "Allow changes on client computers". If this flag is set, the settings in the public profile can be overwritten on client computers. The overwritten settings are kept in registry on client computers.

Private profiles are visible only on the computer where they were created. With private profiles, the generated PDF files are always sent to the computer that initiated the print job. Private profiles are kept in registry on client computer (HKEY_CURRENT_USER).

2.3.5 How to register for messages

novaPDF Printer driver generates the following events when processing a print job:

- Document Started
- Page Started
- Page Ended
- Document Ended
- File Sent
- File Saved
- Print Error
- Email Sent

- Email Error

When the events are fired by the driver, these Windows messages are sent to a registered window handler. To receive a message you need to register your window handle with the RegisterEventWindow method. See the MFC Converter and MFC Scribble samples.

These events are fired when the print job is processed by the driver. When an application sends a print job to the printer, the print job is added in the printer spooler queue. There might be other jobs waiting in the queue that have to be finished before your job starts. So there might be some delay between the moment the application is sending the job to the printer, the moment the job is actually processed and the time when the PDF file is saved. If you need for instance to open the PDF file afterwards, you need to register to the File Saved message and process the PDF file in this message handler.

2.3.6 How to use events

If you want to wait for a print job to be finished, you can register some Windows events and wait for them to be signaled by novaPDF Printer.

Before starting the print job, you have to inform novaPDF that you want to be wait for an event. Call RegisterNovaEvent(LPCWSTR p_wsEventName) with one one of the next strings:

```
NOVAPDF_EVENT_START_DOC
NOVAPDF_EVENT_END_DOC
NOVAPDF_EVENT_FILE_SAVED
```

After you send the job to the printer, call WaitForNovaEvent(ULONG p_nMilliseconds). This function will return when the event was signaled or when the time was elapsed.

If you just want to be sure that the print job was started, the profile was read, and you want to proceed modifying the profile for the next job, you should wait for the NOVAPDF_EVENT_START_DOC event. If you are interested where the PDF file is ready so you can do further actions with it, you should wait for the NOVAPDF_EVENT_FILE_SAVED event.

2.3.7 Reference

2.3.7.1 Registry keys

novaPDF Printer settings are saved in the following registry key:

HKEY_CURRENT_USER\Software\Softland\novaPDF\Printers\novaPDF Pro\Profiles\Default Profile

There are different keys for each installed printer, and there might be also other profiles beside the Default Profile. Each profile has following keys:

Page

Registry key	Type	Possible values	Default value
Page Form	string	A4, Letter, Legal, etc.	
Margin Left	int	left margin in millimeters * 1000	0
Margin Top	int	top margin in millimeters * 1000	0
Margin Right	int	right margin in millimeters * 1000	0

Margin Bottom	int	bottom margin in millimeters * 1000	0
Origin Top	int	page top origin in millimeters * 1000	0
Origin Left	int	page left origin in millimeters * 1000	0
Align Right Margin	int	0 - false; 1 - true	0
Align Bottom Margin	int	0 - false; 1 - true	0
Center Horizontally	int	0 - false; 1 - true	0
Center Vertically	int	0 - false; 1 - true	0
Fit Zoom to Margins	int	0 - false; 1 - true	0
Page Width	int	page width in millimeters * 1000	
Page Height	int	page height in millimeters * 1000	
Page Orientation	int	1 - portrait; 2 - landscape	1
Page Resolution	int	resolution in dpi	300
Page Scale	int	1-400 %	100
Page Zoom	int	25.000-400.000, (25% - 400%)	100.000 (100%)
Page Units	int	0 - inches; 1 - millimeters; 2 - points	1
Page Size	int	one of the defines from wingdi.h (DMPAPER_A4, DMPAPER_LETTER, etc.)	1
Calculate CropBox	int	0 - false; 1 - true	0

Compression settings

Registry key	Type	Possible values	Default value
Use Text Compression	int	0 - false; 1 - true	1
Use Image Compression	int	0 - false; 1 - true	1
Use Monochrome Image Compression	int	0 - false; 1 - true	1
Use Indexed Image Compression	int	0 - false; 1 - true	1
Text Compression Method	int	0 - zip compression	0
Text Compression Level	int	1-9	6
Image Compression Method	int	0 - zip compression 1 - JPEG compression	1
Image Compression Level	int	1-9 if "Image Compression Method" is zip, or 10-100 if "Image Compression Method" is JPEG	6 or 75

Indexed Compression Method	int	0 - zip compression	0
Indexed Compression Level	int	1-9	6
Monochrome Compression Method	int	0 - zip compression	0
Monochrome Compression Level	int	1-9	6
Correct Line Widths	int	0 - false; 1 - true	0
Image Optimization	int	0 - false; 1 - true	0

Graphics settings

Registry key	Type	Possible values	Default value
Graphics Configuration	int	0 - Compression 1 - Downsample 2 - Greyscale 3 - Monochrome 4 - None 5 - Custom	0
Downsample High Color Img	int	0 - false; 1 - true	0
Downsample High Color Img DPI	int	72 - 2400	96
Downsample High Color Img Type	int	0 - BOX Filter 1 - BILINEAR Filter 2 - BSPLINE Filter 3 - BICUBIC Filter 4 - CATMULLROM Filter 5 - LANCZOS3 Filter	3
Downsample Indexed Img	int	0 - false; 1 - true	0
Downsample Indexed Img DPI	int	72 - 2400	96
Downsample Indexed Img Type	int	0 - BOX Filter 1 - BILINEAR Filter 2 - BSPLINE Filter 3 - BICUBIC Filter 4 - CATMULLROM Filter 5 - LANCZOS3 Filter	3
Downsample Monochrome Img	int	0 - false; 1 - true	0
Downsample Monochrome Img DPI	int	72 - 2400	96
Downsample Monochrome Img Type	int	0 - BOX Filter 1 - BILINEAR Filter 2 - BSPLINE Filter 3 - BICUBIC Filter 4 - CATMULLROM Filter 5 - LANCZOS3 Filter	3
Convert High Color Img	int	0 - false; 1 - true	0
Convert Indexed Img	int	0 - false; 1 - true	0
Convert High Color Img Type	int	0 - Grayscale 1 - Monochrome	0
Dither High Color Img	int	0 - false; 1 - true	1
Dither High Color Img Method	int	0 - FS Dither 1 - BAYER4 Dither	0

		2 - BAYER8 Dither 3 - ORDER6 Dither 4 - ORDER8 Dither 5 - ORDER16 Dither	
Convert Indexed Img Type	int	0 - Grayscale 1 - Monochrome	0
Dither Indexed Img	int	0 - false; 1 - true	1
Dither Indexed Img Method	int	0 - FS Dither 1 - BAYER4 Dither 2 - BAYER8 Dither 3 - ORDER6 Dither 4 - ORDER8 Dither 5 - ORDER16 Dither	0
Convert Text and Graphics	int	0 - false; 1 - true	0
Convert Text and Graphics Type	int	0 - Grayscale 1 - Monochrome	0
Convert Monochrome Text Trashold	int	0 - 255	128
Convert High Color Img Trashold	int	0 - 255	128
Convert Indexed Img Trashold	int	0 - 255	128

Fonts

Registry key	Type	Possible values	Default value
Embed All Fonts	int	0 - false; 1 - true	0
Embed Font Subset	int	0 - false; 1 - true	1
Use Embed Fonts List	int	0 - false; 1 - true	0
Use Never Embed Fonts List	int	0 - false; 1 - true	1
Always Embed Fonts List	string	font names separated by ";"	
Never Embed Fonts List		font names separated by ";"	Arial;Courier; Times New Roman;

Document Info

Registry key	Type	Possible values	Default value
Document Author	string		"<Default>"
Document Creator	string		
Document Keywords	string		
Document Subject	string		
Document Title	string		"<Default>"
Document Page Layout	int	0 - single page; 1 - continuous; 2 - facing; 3 - continuous facing;	1
Document Page Mode	int	0 - show page only;	0

		1 - show bookmarks panel; 2 - show pages panel; 3 - show layers panel; 4 - show attachments panel; 5 - full screen mode	
Document Page Number	int		0
Document Page Magnification	int	0 - Default viewer settings; 1 - Fit Width; 2 - Fit Height; 3 - Fit Page; 4 - Percent;	0
Document Magnification Percent	int		100
Document Creation Day	int		0
Document Creation Year	int		0
Document Creation Month	int		0
Document Creation Hour	int		0
Document Creation Minute	int		0
Document Creation Second	int		0
Document Modify Day	int		0
Document Modify Year	int		0
Document Modify Month	int		0
Document Modify Hour	int		0
Document Modify Minute	int		0
Document Modify Second	int		0

Security

Registry key	Type	Possible values	Default value
AllowPrint	int	0 - false; 1 - true	0
AllowModify	int	0 - false; 1 - true	0
AllowCopyExtract	int	0 - false; 1 - true	0
AllowAnnotForms	int	0 - false; 1 - true	0
AllowFillFormsRev3	int	0 - false; 1 - true	0
AllowExtractRev3	int	0 - false; 1 - true	0
AllowModPagesRev3	int	0 - false; 1 - true	0
AllowPrintRev3	int	0 - false; 1 - true	0
User Password	string (encrypted)		
Owner Password	string (encrypted)		
Level	int	0 - no security; 1 - 40 bits encryption;	0

		2 - 128 bits encryption	
--	--	-------------------------	--

Links

Registry key	Type	Possible values	Default value
AnalyzeUrl	int	0 - false; 1 - true	1
DetectFiles	int	0 - false; 1 - true	1
BorderType	int	0 - no border; 1 - underline; 2 - rectangle	0
BorderStyle	int	0 - solid; 1 - dashed	0
BorderWidth	int	border width in points * 1000	1000
BorderColor	int	RGB value	13369344 (0,0,204)
UseLinkColor	int	0 - false; 1 - true	0
CheckFileExists	int	0 - false; 1 - true	0

Email

Registry key	Type	Possible values	Default value
Send Email	int	0 - false; 1 - true	0
Email Type	int	0 - Send with default email client 1 - Open default email client 2 - Send with SMTP	0
Email Compress PDF	int	0 - false; 1 - true	0
Email To Address	string		
Email CC Address	string		
Email BCC Address	string		
Email Subject	string		
Email Body	string		
Email From Address	string		
Email SMTP Server	string		
Email SMTP Port	int		25
Email SMTP User	string		
Email SMTP Password	string (encrypted)		
Email SMTP Authentication	int	0 - false; 1 - true	0
Email SMTP SSL	int	0 - false; 1 - true	0

Watermarks

Registry key	Type	Possible values	Default value
Enable Watermarks	int	0 - false; 1 - true	0

Bookmarks

Registry key	Type	Possible values	Default value
Bookmarks Detection Enabled	int	0 - false; 1 - true	0
Bookmarks Allow Multi-Line	int	0 - false; 1 - true	0
Bookmarks Match Nodes Regardless of Level	int	0 - false; 1 - true	0
Bookmarks Number of Levels to Consider	int		0
Bookmarks Open up to Level	int		0

Save

Registry key	Type	Possible values	Default value
Save Local	int	0 - false; 1 - true	1
Prompt Save Dialog	int	0 - false; 1 - true	1
Save Folder	string		
Save File	string	save file name or a valid macro	[N]
File Conflict Strategy	int	0 - prompt save as dialog; 1 - autonumber new; 2 - append date-time; 3 - overwrite; 4 - auto number existing files;	0
Save Folder Ask	string		
Save File Ask	string	save file name or a valid macro	[N]
Post Save Open	int	0 - false; 1 - true	1
Use Default Viewer	int	0 - false; 1 - true	1
Action Application	string		
Action Arguments	string		

Global settings

Registry key	Type	Possible values	Default value
ActiveProfile	string	name of the active profile	"Default Profile"
ActiveProfilePublic	int	0 - false; 1 - true	0
AskSaveProfile	int	0 - false; 1 - true	1
OverridePaper	int	0 - false; 1 - true	0
SilentPrint	int	0 - false; 1 - true	0

AllowChangeProfile	int	0 - false; 1 - true	0
PublicProfile	int	0 - false; 1 - true	0
PDFVersion	int	3 - PDF 1.3 (Adobe Reader 4) 4 - PDF 1.4 (Adobe Reader 5) 5 - PDF 1.5 (Adobe Reader 6) 6 - PDF 1.6 (Adobe Reader 7)	4
PropagateDefaultProfile	int	0 - false; 1 - true	0
ShowPrivateProfiles	int	0 - false; 1 - true	1

SDK - registered window for messages

Registry key	Type	Possible values	Default value
EventsWindow	int	handle to window to receive printer events	0

2.3.7.2 Windows messages

novaPDF Printer messages

Message name	Event	WPARAM	LPARAM
NOVAPDF2_STARTDOC	sent when the printer driver begins processing the print job and generating the PDF file	0	jobID
NOVAPDF2_ENDDOC	sent when the printer driver finished processing the print job	0	jobID
NOVAPDF2_STARTPAGE	sent when the printer driver starts processing a new page	0	jobID
NOVAPDF2_ENDPAGE	sent when the printer driver finished processing a page	0	jobID
NOVAPDF2_FILESENT	sent when the printer driver finished generating the PDF file and sent it to the computer that started the print job	0	jobID
NOVAPDF2_FILESAVED	sent when the PDF file is received and saved by the computer that started the print job	0	jobID
NOVAPDF2_PRINTERROR	sent when an error occurred during the print job	error no.	jobID
NOVAPDF2_EMAILSENT	sent when the email option is enabled and a email with the generated PDF file was sent	0	jobID
NOVAPDF2_EMAILERROR	sent when the email option is enabled and there was an error sending the email with the	0	jobID

	generated PDF file		
--	--------------------	--	--

The following error numbers are sent by the printer driver, in the NOVAPDF2_PRINTERROR event:

- 1 - Error saving temporary PDF file on the printer server.
- 2 - Error reading license information on the printer server.
- 3 - Error generating the PDF file.
- 4 - Print job was canceled
- 5 - Licensing error: too many copies running with the same license
- 6 - Client computer is not licensed
- 7 - Error sending email
- 8 - Error reading active profile from client computer

How to register windows messages

You can register windows messages using RegisterWindowMessage function. Here are some samples of how to do it:

MFC Converter
VCL Converter
VB Converter

2.3.7.3 What is INovaPdfOptions

The INovaPdfOptions interface represents a COM object that allows the developers to set printing parameters for novaPDF Printer. This interface is derived from **IDispatch** interface directly.

This interface resides in the "novapi2.dll" module, that is distributed with the novaPDF SDK and is registered at install time.

INovaPdfOptions has next methods:

Initialization

Initialize
Initialize2
InitializeSilent
InitializeSilent2

Get / Set Options

GetOptionString
GetOptionString2
GetOptionEncString
GetOptionEncString2
SetOptionString
SetOptionString2
SetOptionEncString
SetOptionEncString2
GetOptionLong
GetOptionLong2
SetOptionLong
SetOptionLong2
AddPredefinedForm
AddPredefinedForm2
GetPredefinedForm
GetPredefinedForm2
RemovePredefinedForm
RemovePredefinedForm2
SetFormVisible
SetFormVisible2
GetFirstForm

GetFirstForm2
GetNextForm
GetNextForm2
AddBookmarkDefinition
AddBookmarkDefinition2
ModifyBookmarkDefinition
ModifyBookmarkDefinition2
DeleteBookmarkDefinition
DeleteBookmarkDefinition2
EnableBookmarkDefinition
EnableBookmarkDefinition2
GetBookmarkDefinition
GetBookmarkDefinition2
GetBookmarkHeaderCount
GetBookmarkHeaderCount2
GetBookmarkDefinitionCount
GetBookmarkDefinitionCount2
AddWatermarkImage
AddWatermarkImage2
ModifyWatermarkImage
ModifyWatermarkImage2
DeleteWatermarkImage
DeleteWatermarkImage2
EnableWatermarkImage
EnableWatermarkImage2
GetWatermarkImage
GetWatermarkImage2
GetWatermarkImageCount
GetWatermarkImageCount2
AddWatermarkText
AddWatermarkText2
ModifyWatermarkText
ModifyWatermarkText2
DeleteWatermarkText
DeleteWatermarkText2
EnableWatermarkText
EnableWatermarkText2
GetWatermarkText
GetWatermarkText2
GetWatermarkTextCount
GetWatermarkTextCount2

Profiles Management

AddProfile
AddProfile2
CopyProfile
CopyProfile2
RenameProfile
RenameProfile2
DeleteProfile
DeleteProfile2
GetFirstProfile
GetFirstProfile2
GetNextProfile
GetNextProfile2
GetActiveProfile
GetActiveProfile2
SetActiveProfile

SetActiveProfile2

Set default printer

SetDefaultPrinter
RestoreDefaultPrinter

Register events

RegisterEventWindow
UnRegisterEventWindow
RegisterNovaEvent
RegisterNovaEvent2
WaitForNovaEvent

OLE Licensing

InitializeOLEUsage
LicenseOLEServer

ShellExecute Licensing

LicenseShellExecuteFile

Print from launched applications

LicenseApplication

2.3.7.4 INovaPdfOptions

2.3.7.4.1 Initialize

The **Initialize** method initializes the INovaPdfOptions interface

```
HRESULT Initialize(
    [in] LPCWSTR p_wsPrinterName,
    [in] LPCWSTR p_wsUserName,
    [in] LPCWSTR p_wsLicenseKey,
    [in] LPCWSTR p_wsApplicationName
);
```

Parameters:

p_wsPrinterName
[in] pointer to a null terminated Unicode string containing the name of the printer

p_wsUserName
[in] pointer to a null terminated Unicode string containing the name of the user

p_wsLicenseKey
[in] pointer to a null terminated Unicode string containing the registration key

p_wsApplicationName
[in] pointer to a null terminated Unicode string containing the application name

Return values:

S_OK on success or COM error code
NV_INVALID_PRINTER_NAME - cannot find printer with given printer name
NV_NOT_A_NOVAPDF_PRINTER - printer is not a novaPDF printer

Remarks:

This method must be called prior to calling any method from the INovaPdfOptions interface.

2.3.7.4.2 Initialize2

The **Initialize2** method initializes the INovaPdfOptions interface

```
HRESULT Initialize2(  
    [in] BSTR p_wsPrinterName,  
    [in] BSTR p_wsUserName,  
    [in] BSTR p_wsLicenseKey,  
    [in] BSTR p_wsApplicationName  
);
```

Parameters:

p_wsPrinterName
[in] pointer to a BSTR containing the name of the printer to configure

p_wsUserName
[in] pointer to a BSTR containing the name of the user to whom this module is registered

p_wsLicenseKey
[in] pointer to a BSTR containing the registration key. This parameter can be a null terminated Unicode string

p_wsApplicationName
[in] pointer to a BSTR containing the application name. This parameter can be a null terminated Unicode string

Return values:

S_OK on success or COM error code
NV_INVALID_PRINTER_NAME - cannot find printer with given printer name
NV_NOT_A_NOVAPDF_PRINTER - printer is not a novaPDF printer

Remarks:

This method must be called prior to calling any method from the INovaPdfOptions interface.

2.3.7.4.3 InitializeSilent

The **InitializeSilent** method initializes the INovaPdfOptions interface silently

```
HRESULT InitializeSilent(  
    [in] LPCWSTR p_wsPrinterName,  
    [in] LPCWSTR p_wsUserName,  
    [in] LPCWSTR p_wsLicenseKey,  
    [in] LPCWSTR p_wsApplicationName  
);
```

Parameters:

p_wsPrinterName
[in] pointer to a null terminated Unicode string containing the name of the printer to configure

p_wsUserName
[in] pointer to a null terminated Unicode string containing the name of the user to whom this module is registered

p_wsLicenseKey
[in] pointer to a null terminated Unicode string containing the registration key

p_wsApplicationName
[in] pointer to a null terminated Unicode string containing the application name

Return values:

S_OK on success or COM error code
NV_INVALID_PRINTER_NAME - cannot find printer with given printer name

NV_NOT_A_NOVAPDF_PRINTER - printer is not a novaPDF printer

Remarks:

This method can be used instead of the Initialize method, when you don't want to have message boxes shown with error messages. Use it when your application runs as a windows service or on a server computer .

2.3.7.4.4 InitializeSilent2

The **InitializeSilent2** method initializes the INovaPdfOptions interface silently

```
HRESULT InitializeSilent2(
    [in] BSTR p_wsPrinterName,
    [in] BSTR p_wsUserName,
    [in] BSTR p_wsLicenseKey,
    [in] BSTR p_wsApplicationName
);
```

Parameters:

p_wsPrinterName
[in] pointer to a BSTR containing the name of the printer to configure

p_wsUserName
[in] pointer to a BSTR containing the name of the user to whom this module is r

p_wsLicenseKey
[in] pointer to a BSTR containing the registration key. This parameter can be a

p_wsApplicationName
[in] pointer to a BSTR containing the application name. This parameter can be a

Return values:

S_OK on success or COM error code
NV_INVALID_PRINTER_NAME - cannot find printer with given printer name
NV_NOT_A_NOVAPDF_PRINTER - printer is not a novaPDF printer

Remarks:

This method can be used instead of the Initialize method, when you don't want to have message boxes shown with error messages. Use it when your application runs as a windows service or on a server computer .

2.3.7.4.5 GetOptionString

The GetOptionString method retrieves a printing option of string type for a given profile

```
HRESULT GetOptionString(
    [in] LPCWSTR p_wsOptionName,
    [out] LPWSTR* p_pwsValue,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wsOptionName
[in] pointer to a null terminated Unicode string containing the name of the opt

p_pwsValue
[out] pointer to a pointer to a null terminated Unicode string that will contain

`p_wsProfileName`
[in] pointer to a null terminated Unicode string containing the profile to use.

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_PROFILE_NOT_FOUND - inexistent profile specified
NV_INVALID_OPTION - unknown option specified

Remarks:

The option names that you can use in the `GetOptionXXXX` and `SetOptionXXXX` functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: `novaOptions.h`, `novaOptions.pas`, `Globals.bas`.

2.3.7.4.6 `GetOptionString2`

The **GetOptionString2** method retrieves a printing option of string type for a given profile

```
HRESULT GetOptionString2(  
    [in] BSTR p_wsOptionName,  
    [out] BSTR* p_pwsValue,  
    [in] BSTR p_wsProfileName,  
    [in] BOOL p_bPublicProfile  
);
```

Parameters:

`p_wsOptionName`
[in] pointer to a BSTR containing the name of the option to set

`p_pwsValue`
[out] pointer to a pointer to BSTR that will contain the value of the retrieved

`p_wsProfileName`
[in] pointer to BSTR containing the profile to use. If this parameter is an emp

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_PROFILE_NOT_FOUND - inexistent profile specified
NV_INVALID_OPTION - unknown option specified

Remarks:

The option names that you can use in the `GetOptionXXXX` and `SetOptionXXXX` functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: `novaOptions.h`, `novaOptions.pas`, `Globals.bas`.

2.3.7.4.7 GetOptionEncString

The **GetOptionEncString** method retrieves a printing option of encrypted string type for a given profile.

```
HRESULT GetOptionEncString(
    [in] LPCWSTR p_wsOptionName,
    [out] LPWSTR* p_pwsValue,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL     p_bPublicProfile
);
```

Parameters:

p_wsOptionName
[in] pointer to a null terminated Unicode string containing the name of the option.

p_pwsValue
[out] pointer to a pointer to a null terminated Unicode string that will contain the value of the option.

p_wsProfileName
[in] pointer to a null terminated Unicode string containing the profile to use.

p_bPublicProfile
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_PROFILE_NOT_FOUND - inexistent profile specified
 NV_INVALID_OPTION - unknown option specified

Remarks:

This method must be called for strings that are kept encrypted in registry (for instance user and owner passwords for the security options).

The option names that you can use in the GetOptionXXXX and SetOptionXXXX functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: novaOptions.h, novaOptions.pas, Globals.bas.

2.3.7.4.8 GetOptionEncString2

The **GetOptionString2** method retrieves a printing option of encrypted string type for a given profile

```
HRESULT GetOptionEncString2(
    [in] BSTR p_wsOptionName,
    [out] BSTR* p_pwsValue,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wsOptionName
[in] pointer to a BSTR containing the name of the option to set

p_pwsValue
[out] pointer to a pointer to BSTR that will contain the value of the retrieved option.

`p_wsProfileName`
[in] pointer to BSTR containing the profile to use. If this parameter is an empty string, the default profile is used.

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_PROFILE_NOT_FOUND - inexistent profile specified
NV_INVALID_OPTION - unknown option specified

Remarks:

This method must be called for strings that are kept encrypted in registry (for instance user and owner passwords for the security options).

The option names that you can use in the `GetOptionXXXX` and `SetOptionXXXX` functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: `novaOptions.h`, `novaOptions.pas`, `Globals.bas`.

2.3.7.4.9 SetOptionString

The **SetOptionString** method sets a printing option of string type for a given profile

```
HRESULT SetOptionString(
    [in] LPCWSTR p_wsOptionName,
    [in] LPCWSTR p_wsValue,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL     p_bPublicProfile
);
```

Parameters:

`p_wsOptionName`
[in] pointer to a null terminated Unicode string containing the name of the option

`p_wsValue`
[in] pointer to a null terminated Unicode string containing the value of the option

`p_wsProfileName`
[in] pointer to a null terminated Unicode string containing the profile to modify

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_PROFILE_NOT_FOUND - inexistent profile specified
NV_INVALID_OPTION - unknown option specified
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

The option names that you can use in the `GetOptionXXXX` and `SetOptionXXXX` functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: `novaOptions.h`, `novaOptions.pas`, `Globals.bas`.

2.3.7.4.10 SetOptionString2

The **SetOptionString2** method sets a printing option of string type for a given profile

```
HRESULT SetOptionString2(
    [in] BSTR p_wsOptionName,
    [in] BSTR p_wsValue,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wsOptionName

[in] pointer to a BSTR containing the name of the option to set

p_wsValue

[in] pointer to a BSTR containing the value of the option to set.

p_wsProfileName

[in] pointer to a BSTR containing the profile to modify. If this parameter is an e

p_bPublicProfile

[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code

NV_NOT_INITIALIZED - Initialize was not called

NV_PROFILE_NOT_FOUND - inexistent profile specified

NV_INVALID_OPTION - unknown option specified

NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

The option names that you can use in the GetOptionXXXX and SetOptionXXXX functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: novaOptions.h, novaOptions.pas, Globals.bas.

2.3.7.4.11 SetOptionEncString

The **SetOptionEncString** method sets a printing option of encrypted string type for a given profile

```
HRESULT SetOptionEncString(
    [in] LPCWSTR p_wsOptionName,
    [in] LPCWSTR p_wsValue,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wsOptionName

[in] pointer to a null terminated Unicode string containing the name of the opt

p_wsValue

[in] pointer to a null terminated Unicode string containing the value of the op

p_wsProfileName

[in] pointer to a null terminated Unicode string containing the profile to modi

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_PROFILE_NOT_FOUND` - inexistent profile specified
`NV_INVALID_OPTION` - unknown option specified
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

Remarks:

This method must be called for strings that are kept encrypted in registry (for instance user and owner passwords for the security options).

The option names that you can use in the `GetOptionXXXX` and `SetOptionXXXX` functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: `novaOptions.h`, `novaOptions.pas`, `Globals.bas`.

2.3.7.4.12 SetOptionEncString2

The **SetOptionEncString2** method sets a printing option of encrypted string type for a given profile

```
HRESULT SetOptionEncString2(  
    [in] BSTR p_wsOptionName,  
    [in] BSTR p_wsValue,  
    [in] BSTR p_wsProfileName,  
    [in] BOOL p_bPublicProfile  
);
```

Parameters:

`p_wsOptionName`
[in] pointer to a BSTR containing the name of the option to set

`p_wsValue`
[in] pointer to a BSTR containing the value of the option to set.

`p_wsProfileName`
[in] pointer to a BSTR containing the profile to modify. If this parameter is a

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_PROFILE_NOT_FOUND` - inexistent profile specified
`NV_INVALID_OPTION` - unknown option specified
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

Remarks:

This method must be called for strings that are kept encrypted in registry (for instance user and owner passwords for the security options).

The option names that you can use in the `GetOptionXXXX` and `SetOptionXXXX` functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: `novaOptions.h`, `novaOptions.pas`, `Globals.bas`.

2.3.7.4.13 GetOptionLong

The **GetOptionLong** method retrieves a printing option of long int type for a given profile

```
HRESULT GetOptionLong(
    [in] LPCWSTR p_wsOptionName,
    [out] LONG* p_plValue,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wsOptionName
[in] pointer to a null terminated Unicode string containing the name of the option

p_plValue
[out] pointer to a long integer that will contain the value of the retrieved option

p_wsProfileName
[in] pointer to a null terminated Unicode string containing the profile to use.

p_bPublicProfile
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_PROFILE_NOT_FOUND - inexistent profile specified
 NV_INVALID_OPTION - unknown option specified

Remarks:

The option names that you can use in the GetOptionXXXX and SetOptionXXXX functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: novaOptions.h, novaOptions.pas, Globals.bas.

2.3.7.4.14 GetOptionLong2

The **GetOptionLong2** method retrieves a printing option of long int type for a given profile

```
HRESULT GetOptionLong2(
    [in] BSTR p_wsOptionName,
    [out] LONG* p_plValue,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wsOptionName
[in] pointer to a BSTR containing the name of the option to set

p_plValue
[out] pointer to a long integer that will contain the value of the retrieved option

p_wsProfileName
[in] pointer to a BSTR containing the profile to use. If this parameter is an empty string, the default profile is used.

p_bPublicProfile
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_PROFILE_NOT_FOUND - inexistent profile specified
 NV_INVALID_OPTION - unknown option specified

Remarks:

The option names that you can use in the GetOptionXXXX and SetOptionXXXX functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: novaOptions.h, novaOptions.pas, Globals.bas.

2.3.7.4.15 SetOptionLong

The **SetOptionLong** method sets a printing option of long int type for a given profile

```
HRESULT SetOptionLong(
    [in] LPCWSTR p_wsOptionName,
    [in] LONG    p_lValue,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL    p_bPublicProfile
);
```

Parameters:

p_wsOptionName
 [in] pointer to a null terminated Unicode string containing the name of the option

p_lValue
 [in] long integer value to set

p_wsProfileName
 [in] pointer to a null terminated Unicode string containing the profile to modify

p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_PROFILE_NOT_FOUND - inexistent profile specified
 NV_INVALID_OPTION - unknown option specified
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

The option names that you can use in the GetOptionXXXX and SetOptionXXXX functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: novaOptions.h, novaOptions.pas, Globals.bas.

2.3.7.4.16 SetOptionLong2

The **SetOptionLong2** method sets a printing option of long int type for a given profile

```
HRESULT SetOptionLong2(
    [in] BSTR p_wsOptionName,
    [in] LONG p_lValue,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

`p_wsOptionName`
[in] pointer to a BSTR containing the name of the option to set

`p_lValue`
[in] long integer value to set

`p_wsProfileName`
[in] pointer to a BSTR containing the profile to modify. If this parameter is a

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_PROFILE_NOT_FOUND` - inexistent profile specified
`NV_INVALID_OPTION` - unknown option specified
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

Remarks:

The option names that you can use in the `GetOptionXXXX` and `SetOptionXXXX` functions are the names of the registry keys from the novaPDF profile. You can find the complete list of option names in the Registry keys chapter. In the Include folder of novaPDF SDK installation folder you can find the definitions for all options in the next files: `novaOptions.h`, `novaOptions.pas`, `Globals.bas`.

2.3.7.4.17 AddProfile

The **AddProfile** method adds a new profile

```
HRESULT AddProfile(
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL    p_bPublicProfile
);
```

Parameters:

`p_wsProfileName`
[in] pointer to a null terminated Unicode string containing the name of the profile

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_PROFILE_EXISTS` - a profile with the same name already exists
`NV_ENOUGH_PROFILES` - too many profiles already, can not add more

Remarks:

The newly created profile contains default settings.

2.3.7.4.18 AddProfile2

The **AddProfile2** method adds a new profile

```
HRESULT AddProfile2(
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

`p_wsProfileName`
[in] pointer to a BSTR containing the name of the profile to add.

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_PROFILE_EXISTS` - a profile with the same name already exists
`NV_ENOUGH_PROFILES` - too many profiles already, can not add more

Remarks:

The newly created profile contains default settings.

2.3.7.4.19 CopyProfile

The **CopyProfile** method copies an existing profile to a new profile.

```
HRESULT CopyProfile(
    [in] LPCWSTR p_wsOldProfileName,
    [in] LPCWSTR p_wsNewProfileName,
    [in] BOOL    p_bPublicProfile
);
```

Parameters:

`p_wsOldProfileName`
[in] pointer to a null terminated Unicode string containing the name of the profile to copy.

`p_wsNewProfileName`
[in] pointer to a null terminated Unicode string containing the name of the copy profile.

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_UNKNOWN_PROFILE` - profile specified by `p_wsOldProfileName` does not exist
`NV_PROFILE_EXISTS` - a profile with the name `p_wsNewProfileName` already exists
`NV_ENOUGH_PROFILES` - too many profiles already, can not add more
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

2.3.7.4.20 CopyProfile2

The **CopyProfile2** method copies an existing profile to a new profile.

```
HRESULT CopyProfile2(
    [in] BSTR p_wsOldProfileName,
    [in] BSTR p_wsNewProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

`p_wsOldProfileName`
[in] pointer to a BSTR containing the name of the profile to copy.

`p_wsNewProfileName`
[in] pointer to a BSTR containing the name of the copy profile.

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_UNKNOWN_PROFILE - profile specified by p_wsOldProfileName does not exist
 NV_PROFILE_EXISTS - a profile with the name p_wsNewProfileName already exists
 NV_ENOUGH_PROFILES - too many profiles already, can not add more
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.21 RenameProfile

The **RenameProfile** method renames an existing profile.

```
HRESULT RenameProfile(
    [in] LPCWSTR p_wsOldProfileName,
    [in] LPCWSTR p_wsNewProfileName,
    [in] BOOL    p_bPublicProfile
);
```

Parameters:

p_wsOldProfileName
 [in] pointer to a null terminated Unicode string containing the name of the profile.
 p_wsNewProfileName
 [in] pointer to a null terminated Unicode string containing the new name of the profile.
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_UNKNOWN_PROFILE - profile specified by p_wsOldProfileName does not exist
 NV_PROFILE_EXISTS - a profile with the name p_wsNewProfileName already exists
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.22 RenameProfile2

The **RenameProfile2** method renames an existing profile.

```
HRESULT RenameProfile2(
    [in] BSTR p_wsOldProfileName,
    [in] BSTR p_wsNewProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wsOldProfileName
 [in] pointer to a BSTR containing the name of the profile to rename.
 p_wsNewProfileName
 [in] pointer to a BSTR containing the new name of the profile.
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_UNKNOWN_PROFILE - profile specified by p_wsOldProfileName does not exist
 NV_PROFILE_EXISTS - a profile with the name p_wsNewProfileName already exists
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.23 DeleteProfile

The **DeleteProfile** method deletes an existing profile.

```
HRESULT DeleteProfile(
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL    p_bPublicProfile
);
```

Parameters:

`p_wsProfileName`
[in] pointer to a null terminated Unicode string containing the name of the profile.
`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_UNKNOWN_PROFILE` - profile specified by `p_wsProfileName` does not exist
`NV_ACTIVE_PROFILE` - can not delete active profile
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

2.3.7.4.24 DeleteProfile2

The **DeleteProfile2** method deletes an existing profile.

```
HRESULT DeleteProfile2(
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

`p_wsProfileName`
[in] pointer to a BSTR containing the name of the profile to delete.
`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_UNKNOWN_PROFILE` - profile specified by `p_wsProfileName` does not exist
`NV_ACTIVE_PROFILE` - can not delete active profile
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

2.3.7.4.25 GetFirstProfile

The **GetFirstProfile** starts an enumeration of profiles, retrieving the name of the first profile in the enumeration.

```
HRESULT GetFirstProfile(
    [out] LPWSTR* p_pwsProfileName,
    [out] BOOL*   p_bPublicProfile
);
```

Parameters:

`p_pwsProfileName`
[out] pointer to a pointer to a null terminated Unicode string containing the name of the first profile.
`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called

Remarks:

GetFirstProfile is used with **GetNextProfile** to retrieve profile names.

Sample usage:

```
hr = GetFirstProfile(&pName);
while (SUCCEEDED(hr) && hr != NV_NO_MORE_PROFILES) {
    // do something with pName
    // ...
    CoTaskMemFree(pName);
    // get next profile if it exists
    hr = GetNextProfile(&pName);
}
```

2.3.7.4.26 GetFirstProfile2

The **GetFirstProfile2** starts an enumeration of profiles, retrieving the name of the first profile in the enumeration.

```
HRESULT GetFirstProfile2(
    [out] BSTR* p_pwsProfileName,
    [out] BOOL* p_bPublicProfile
);
```

Parameters:

p_pwsProfileName
 [out] pointer to a pointer to a BSTR containing the name of the first existing
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called

Remarks:

GetFirstProfile2 is used with **GetNextProfile2** to retrieve profile names.

Sample usage:

```
hr = GetFirstProfile2(&pName);
while (SUCCEEDED(hr) && hr != NV_NO_MORE_PROFILES) {
    // do something with pName
    // ...
    SysFreeString(pName);
    // get next profile if it exists
    hr = GetNextProfile2(&pName);
}
```

2.3.7.4.27 GetNextProfile

The **GetNextProfile** continues an enumeration of profiles started with **GetFirstProfile**, retrieving the name of the next profile in the enumeration.

```
HRESULT GetNextProfile(
    [out] LPWSTR* p_pwsProfileName,
    [out] BOOL* p_bPublicProfile
);
```

Parameters:

p_pwsProfileName
 [out] pointer to a pointer to a null terminated Unicode string containing the n

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called

Remarks:

`GetNextProfile` is used with `GetFirstProfile` to retrieve profile names.

Sample usage:

```
hr = GetFirstProfile(&pName);
while (SUCCEEDED(hr) && hr != NV_NO_MORE_PROFILES) {
    // do something with pName
    // ...
    CoTaskMemFree(pName);
    // get next profile if it exists
    hr = GetNextProfile(&pName);
}
```

2.3.7.4.28 `GetNextProfile2`

The **`GetNextProfile2`** continues an enumeration of profiles started with `GetFirstProfile2`, retrieving the name of the next profile in the enumeration.

```
HRESULT GetNextProfile2(
    [out] BSTR* p_pwsProfileName,
    [out] BOOL* p_bPublicProfile
);
```

Parameters:

`p_pwsProfileName`
[out] pointer to a pointer to a BSTR containing the name of the next existing profile.
`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called

Remarks:

`GetNextProfile2` is used with `GetFirstProfile2` to retrieve profile names.

Sample usage:

```
hr = GetFirstProfile2(&pName);
while (SUCCEEDED(hr) && hr != NV_NO_MORE_PROFILES) {
    // do something with pName
    // ...
    SysFreeString(pName);
    // get next profile if it exists
    hr = GetNextProfile2(&pName);
}
```

2.3.7.4.29 `GetActiveProfile`

The **`GetActiveProfile`** retrieves the name of the active profile (i.e. the profile that is used for printing).

```
HRESULT GetActiveProfile(
    [out] LPWSTR* p_pwstrActiveProfile
    [out] BOOL* p_bPublicProfile
);
```

Parameters:

p_pwstrActiveProfile
 [out] pointer to a pointer to a null terminated Unicode string that will contain the name of the active profile.
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called

2.3.7.4.30 GetActiveProfile2

The **GetActiveProfile2** retrieves the name of the active profile (i.e. the profile that is used for printing).

```
HRESULT GetActiveProfile2(
    [out] BSTR* p_pwstrActiveProfile
    [out] BOOL* p_bPublicProfile
);
```

Parameters:

p_pwstrActiveProfile
 [out] pointer to a pointer to a BSTR that will contain the name of the active profile.
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called

2.3.7.4.31 SetActiveProfile

The **SetActiveProfile** sets the active profile (i.e. the profile that will be used for printing).

```
HRESULT SetActiveProfile(
    [in] LPWSTR* p_wstrProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wstrProfileName
 [in] pointer to a null terminated Unicode string that contains the name of the profile.
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_UNKNOWN_PROFILE - the profile specified by p_wstrProfileName does not exist

2.3.7.4.32 SetActiveProfile2

The **SetActiveProfile2** sets the active profile (i.e. the profile that will be used for printing).

```
HRESULT SetActiveProfile2(
    [in] BSTR* p_wstrProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wstrProfileName
 [in] pointer to a BSTR that contains the name of the profile that is to be set

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_UNKNOWN_PROFILE` - the profile specified by `p_wstrProfileName` does not exist

2.3.7.4.33 AddPredefinedForm

The **AddPredefinedForm** method adds a new custom user defined form, having the characteristics specified by the method parameters.

```
HRESULT AddPredefinedForm(
    [in] LPCWSTR p_wsFormName,
    [in] LPCWSTR p_wsDescription,
    [in] FLOAT p_fWidth,
    [in] FLOAT p_fHeight,
    [in] BOOL p_bVisible,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

`p_wsFormName`
[in]pointer to a null terminated Unicode string containing the name of the custom form

`p_wsDescription`
[in]pointer to a null terminated Unicode string containing the form description

`p_fWidth`
[in]form width in millimeters

`p_fHeight`
[in]form height in millimeters

`p_bVisible`
[in] specifies whether this form is visible in the forms combo box in the print dialog

`p_wsProfileName`
[in] pointer to a null terminated Unicode string containing the profile to modify

`p_bPublicProfile`
[in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_PROFILE_EXISTS` - a profile with the same name already exists
`NV_ENOUGH_PROFILES` - too many profiles already, can not add more
`NV_FORM_EXISTS` - a form with the specified name already exists
`NV_ENOUGH_FORMS` - the maximum number of custom forms has been reached
`NV_INVALID_WIDTH` - width should be in the range 1cm - 10m
`NV_INVALID_HEIGHT` - height should be in the range 1cm - 10m
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

2.3.7.4.34 AddPredefinedForm2

The **AddPredefinedForm2** method adds a new custom user defined form, having the characteristics specified by the method parameters.

```
HRESULT AddPredefinedForm2(
    [in] BSTR p_wsFormName,
    [in] BSTR p_wsDescription,
    [in] FLOAT p_fWidth,
    [in] FLOAT p_fHeight,
```

```

    [in] BOOL p_bVisible,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_wsFormName
[in] pointer to a BSTR containing the name of the custom form to add

p_wsDescription
[in] pointer to a BSTR containing the form description

p_fWidth
[in] form width in millimeters

p_fHeight
[in] form height in millimeters

p_bVisible
[in] specifies whether this form is visible in the forms combo box in the print

p_wsProfileName
[in] pointer to a BSTR containing the profile to modify. If this parameter is a

p_bPublicProfile
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code

NV_NOT_INITIALIZED - Initialize was not called

NV_PROFILE_EXISTS - a profile with the same name already exists

NV_ENOUGH_PROFILES - too many profiles already, can not add more

NV_FORM_EXISTS - a form with the specified name already exists

NV_ENOUGH_FORMS - the maximum number of custom forms has been reached

NV_INVALID_WIDTH - width should be in the range 1cm - 10m

NV_INVALID_HEIGHT - height should be in the range 1cm - 10m

NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.35 GetPredefinedForm

The **GetPredefinedForm** retrieves information about a predefined custom form, given the form name.

```

HRESULT AddPredefinedForm(
    [in] LPCWSTR p_wsFormName,
    [out] LPWSTR* p_pwsFormDescription,
    [out] FLOAT* p_pfWidth,
    [out] FLOAT* p_pfHeight,
    [out] BOOL* p_pbVisible,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_wsFormName
[in] pointer to a null terminated Unicode string containing the name of the cust

p_pwsFormDescription
[out] pointer to a pointer to a null terminated Unicode string that will contain

p_pfWidth
[out] will contain the form width in millimeters

p_pfHeight
[out] will contain the form height in millimeters

p_pbVisible
[out] specifies whether this form is visible in the forms combo box in the print

p_wsProfileName

[in] pointer to a null terminated Unicode string containing the profile to modify
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_UNKNOWN_FORM - a form with the specified name does not exist

2.3.7.4.36 GetPredefinedForm2

The **GetPredefinedForm2** retrieves information about a predefined custom form, given the form name.

```
HRESULT AddPredefinedForm2(
    [in] BSTR    p_wsFormName,
    [out] BSTR*  p_pwsFormDescription,
    [out] FLOAT* p_pfWidth,
    [out] FLOAT* p_pfHeight,
    [out] BOOL*  p_pbVisible,
    [in] BSTR    p_wsProfileName,
    [in] BOOL    p_bPublicProfile
);
```

Parameters:

p_wsFormName
 [in] pointer to a BSTR containing the name of the custom form to add
 p_pwsFormDescription
 [out] pointer to a pointer to a BSTR that will contain the form description. The
 p_pfWidth
 [out] will contain the form width in millimeters
 p_pfHeight
 [out] will contain the form height in millimeters
 p_pbVisible
 [out] specifies whether this form is visible in the forms combo box in the print
 p_wsProfileName
 [in] pointer to a BSTR containing the profile to modify. If this parameter is a
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_UNKNOWN_FORM - a form with the specified name does not exist

2.3.7.4.37 RemovePredefinedForm

The **RemovePredefinedForm** method deletes a user defined form with a given name

```
HRESULT RemovePredefinedForm(
    [in] LPCWSTR p_wsFormName,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL    p_bPublicProfile
);
```

Parameters:

p_wsFormName
 [in] pointer to a null terminated Unicode string containing the name of the custom
 p_wsProfileName
 [in] pointer to a null terminated Unicode string containing the profile to modify

`p_bPublicProfile`
 [in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_UNKNOWN_FORM` - a form with the specified name does not exist
`NV_READONLY_FORM` - can not deleted a system form
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

2.3.7.4.38 RemovePredefinedForm2

The **RemovePredefinedForm2** method deletes a user defined form with a given name

```
HRESULT RemovePredefinedForm2(
    [in] BSTR p_wsFormName,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

`p_wsFormName`
 [in] pointer to a BSTR containing the name of the custom form to delete
`p_wsProfileName`
 [in] pointer to a BSTR containing the profile to modify. If this parameter is a
`p_bPublicProfile`
 [in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_UNKNOWN_FORM` - a form with the specified name does not exist
`NV_READONLY_FORM` - can not deleted a system form
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

2.3.7.4.39 SetFormVisible

The **SetFormVisible** method sets the visibility of a form in the forms combo-box on the printer preferences dialog.

```
HRESULT SetFormVisible(
    [in] LPCWSTR p_wsFormName,
    [in] BOOL p_bVisible,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

`p_wsFormName`
 [in] pointer to a null terminated Unicode string containing the name of the custom form
`p_bVisible`
 [in] set to TRUE to show form or FALSE to hide form.
`p_wsProfileName`
 [in] pointer to a null terminated Unicode string containing the profile to modify
`p_bPublicProfile`
 [in] Flag if the profile is a public or a private profile.

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called

NV_UNKNOWN_FORM - a form with the specified name does not exist
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.40 SetFormVisible2

The **SetFormVisible2** method sets the visibility of a form in the forms combo-box on the printer preferences dialog.

```
HRESULT SetFormVisible2(
    [in] BSTR p_wsFormName,
    [in] BOOL p_bVisible,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_wsFormName
 [in] pointer to a BSTR containing the name of the custom form to edit

p_bVisible
 [in] set to TRUE to show form or FALSE to hide form.

p_wsProfileName
 [in] pointer to a BSTR containing the profile to modify. If this parameter is a

p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_UNKNOWN_FORM - a form with the specified name does not exist
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.41 GetFirstForm

The **GetFirstForm** method starts an enumeration of forms, retrieving the name and the properties of the first form in the enumeration.

```
HRESULT GetFirstForm(
    [out] LPWSTR* p_pwsFormName,
    [out] LPWSTR* p_pwsFormDescription,
    [out] FLOAT* p_pfWidth,
    [out] FLOAT* p_pfHeight,
    [out] BOOL* p_pbVisible,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_pwsFormName
 [out] pointer to a pointer to a null terminated Unicode string that will contain

p_pwsFormDescription
 [out] pointer to a pointer to a null terminated Unicode string that will contain

p_pfWidth
 [out] will contain the width of the form in millimeters

p_pfHeight
 [out] will contain the height of the form in millimeters

p_pbVisible
 [out] will be TRUE if this form is visible in the printing preferences dialog

p_wsProfileName
 [in] pointer to a null terminated Unicode string containing the profile to modify

p_bPublicProfile

[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_NO_MORE_FORMS - no more forms to enumerate

Remarks:

GetFirstForm along with GetNextForm are used to enumerate all custom forms like in the code sample below:

```
hr = GetFirstForm(&pName, ...)
while (SUCCEEDED(hr) && hr != NV_NO_MORE_FORMS) {
    // do something with pName, and the other parameters
    // ...
    CoTaskMemFree(pName);
    // get next form if it exists
    hr = GetNextForm(&pName);
}
```

2.3.7.4.42 GetFirstForm2

The **GetFirstForm2** method starts an enumeration of forms, retrieving the name and the properties of the first form in the enumeration.

```
HRESULT GetFirstForm2(
    [out] BSTR* p_pwsFormName,
    [out] BSTR* p_pwsFormDescription,
    [out] FLOAT* p_pfWidth,
    [out] FLOAT* p_pfHeight,
    [out] BOOL* p_pbVisible,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_pwsFormName
 [out]pointer to a pointer to a BSTR that will contain the name of the custom form
 p_pwsFormDescription
 [out]pointer to a pointer to a BSTR that will contain the description of the custom form
 p_pfWidth
 [out] will contain the width of the form in millimeters
 p_pfHeight
 [out] will contain the height of the form in millimeters
 p_pbVisible
 [out] will be TRUE if this form is visible in the printing preferences dialog
 p_wsProfileName
 [in] pointer to a BSTR containing the profile to modify. If this parameter is a null BSTR, the profile is the default profile.
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_NO_MORE_FORMS - no more forms to enumerate

Remarks:

GetFirstForm2 along with GetNextForm2 are used to enumerate all custom forms like in the code sample below:

```
hr = GetFirstForm2(&pName, ...)
while (SUCCEEDED(hr) && hr != NV_NO_MORE_FORMS) {
```

```

    // do something with pName, and the other parameters
    // ...
    SysFreeString(pName);
    // get next form if it exists
    hr = GetNextForm2(&pName);
}

```

2.3.7.4.43 GetNextForm

The **GetNextForm** continues the custom forms enumeration started with `GetFirstForm`.

```

HRESULT GetNextForm(
    [out] LPWSTR* p_pwsFormName,
    [out] LPWSTR* p_pwsFormDescription,
    [out] FLOAT* p_pfWidth,
    [out] FLOAT* p_pfHeight,
    [out] BOOL* p_pbVisible
);

```

Parameters:

`p_pwsFormName`
[out] pointer to a pointer to a null terminated Unicode string that will contain the form name

`p_pwsFormDescription`
[out] pointer to a pointer to a null terminated Unicode string that will contain the form description

`p_pfWidth`
[out] will contain the width of the form in millimeters

`p_pfHeight`
[out] will contain the height of the form in millimeters

`p_pbVisible`
[out] will be TRUE if this form is visible in the printing preferences dialog

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_ENUM_NOT_INIT` - `GetFirstForm` was not called
`NV_NO_MORE_FORMS` - no more forms to enumerate

Remarks:

`GetFirstForm` along with `GetNextForm` are used to enumerate all custom forms like in the code sample below:

```

hr = GetFirstForm(&pName, ...)
while (SUCCEEDED(hr) && hr != NV_NO_MORE_FORMS) {
    // do something with pName, and the other parameters
    // ...
    CoTaskMemFree(pName);
    // get next form if it exists
    hr = GetNextForm(&pName);
}

```

2.3.7.4.44 GetNextForm2

The **GetNextForm2** continues the custom forms enumeration started with `GetFirstForm2`.

```

HRESULT GetNextForm2(
    [out] BSTR* p_pwsFormName,
    [out] BSTR* p_pwsFormDescription,
    [out] FLOAT* p_pfWidth,
    [out] FLOAT* p_pfHeight,
    [out] BOOL* p_pbVisible
);

```

Parameters:

p_pwsFormName
 [out] pointer to a pointer to a null terminated Unicode string that will contain
 p_pwsFormDescription
 [out] pointer to a pointer to a null terminated Unicode string that will contain
 p_pfWidth
 [out] will contain the width of the form in millimeters
 p_pfHeight
 [out] will contain the height of the form in millimeters
 p_pbVisible
 [out] will be TRUE if this form is visible in the printing preferences dialog

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_ENUM_NOT_INIT - GetFirstForm2 was not called
 NV_NO_MORE_FORMS - no more forms to enumerate

Remarks:

GetFirstForm2 along with GetNextForm2 are used to enumerate all custom forms like in the code sample below:

```

hr = GetFirstForm2(&pName, ...)
while (SUCCEEDED(hr) && hr != NV_NO_MORE_FORMS) {
    // do something with pName, and the other parameters
    // ...
    SysFreeString(pName);
    // get next form if it exists
    hr = GetNextForm2(&pName);
}
  
```

2.3.7.4.45 SetDefaultPrinter

The **SetDefaultPrinter** method sets the current printer (the one specified in Initialize) as default printer.

```
HRESULT SetDefaultPrinter(void);
```

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called

Remarks:

After calling **SetDefaultPrinter** with an INovaPdfOptions object, call RestoreDefaultPrinter with the same object to restore the original default printer. Do not call **SetDefaultPrinter** twice, without calling RestoreDefaultPrinter between the calls or else the original default printer will not be restored.

2.3.7.4.46 RestoreDefaultPrinter

The **RestoreDefaultPrinter** method restores the default printer to the printer that was default before calling SetDefaultPrinter.

```
HRESULT RestoreDefaultPrinter(void);
```

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_NODEFAULT_PRINTER - SetDefaultPrinter was not called

Remarks:

After calling `SetDefaultPrinter` with an `INovaPdfOptions` object, call `RestoreDefaultPrinter` with the same object to restore the original default printer.

2.3.7.4.47 `RegisterEventWindow`

The **RegisterEventWindow** registers a window with the printer in order to receive printing messages.

```
HRESULT RegisterEventWindow(  
    [in] LONG p_hWnd  
);
```

Parameters:

`p_hWnd`
[in] handle to the window (cast to a LONG value), that will receive the printer

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called

2.3.7.4.48 `UnRegisterEventWindow`

The **UnRegisterEventWindow** unregisters the window registered with `RegisterEventWindow` so it will no longer receive printing messages.

```
HRESULT UnRegisterEventWindow(void);
```

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called

2.3.7.4.49 `RegisterNovaEvent`

The **RegisterNovaEvent** registers a Windows event that will be signaled by the printer

```
HRESULT RegisterNovaEvent(  
    [in] LPCWSTR p_wsEventName  
);
```

Parameters:

`p_wsEventName`
[in] Name of the event. See `How to use events` topic for a list of possible even

Return values:

`S_OK` - on success
`S_FALSE` - event cannot be created

2.3.7.4.50 `RegisterNovaEvent2`

The **RegisterNovaEvent2** registers a Windows event that will be signaled by the printer

```
HRESULT RegisterNovaEvent2(  
    [in] BSTR p_wsEventName  
);
```

Parameters:

`p_wsEventName`
[in] Name of the event. See `How to use events` topic for a list of possible even

Return values:

`S_OK` - on success

S_FALSE - event cannot be created

2.3.7.4.51 WaitForNovaEvent

The **WaitForNovaEvent** waits for a Windows event that will be signaled by the printer

```
HRESULT WaitForNovaEvent(
    [in] LONG p_nMilliseconds
);
```

Parameters:

p_nMilliseconds
[in] Number of milliseconds to wait for the event. See How to use events for more information.

Return values:

S_OK - on success
S_FALSE - event was not found

2.3.7.4.52 InitializeOLEUsage

The **InitializeOLEUsage** method initializes the OLE server licensing

```
HRESULT InitializeOLEUsage(
    [in] BSTR p_pwstrOLEProgID,
);
```

Parameters:

p_pwstrOLEProgID
[in] pointer to a Unicode string containing the ProgID for the OLE server that will be used.

Return values:

S_OK on success or COM error code

Remarks:

This method must be called prior to initializing the OLE object that will perform the print to the novaPDF Printer.

2.3.7.4.53 LicenseOLEServer

The **LicenseOLEServer** method license the OLE server prior initialized with InitializeOLEServer

```
HRESULT LicenseOLEServer(void);
```

Return values:

S_OK on success or COM error code

Remarks:

This method must be called after initializing the OLE object that will perform the print to the novaPDF Printer

2.3.7.4.54 LicenseShellExecuteFile

The **LicenseShellExecuteFile** method licences a document to be printed with ShellExecute

```
HRESULT LicenseShellExecuteFile(
    [in] BSTR p_pwstrFileName,
);
```

Parameters:

p_pwstrFileName
[in] pointer to a Unicode string containing the name of the file that will be printed.

Return values:

S_OK on success or COM error code

Remarks:

This method must be called prior to calling the ShellExecute function for the given parameter. This call assures that the document will be printed without the notice on bottom of pages, even if the application that prints the document is already opened.

2.3.7.4.55 LicenseApplication

The **LicenseApplication** method licences an application to print to novaPDF

```
HRESULT LicenseApplication(
    [in] BSTR p_pwstrAppName,
);
```

Parameters:

p_pwstrAppName
[in] pointer to a Unicode string containing the name of the application that will be licensed

Return values:

S_OK on success or COM error code

Remarks:

This method must be called prior to launching the application with the specified name. This call assures that the application will print without the notice on bottom of pages.

2.3.7.4.56 AddBookmarkDefinition

The **AddBookmarkDefinition** method adds a new bookmark definition, having the characteristics specified by the method parameters.

```
HRESULT AddBookmarkDefinition(
    [in] SHORT p_nHeading,
    [in] BOOL p_bEnabled,
    [in] BOOL p_bDetFont,
    [in, string] LPCWSTR p_wsDetFont,
    [in] BOOL p_bDetStyle,
    [in] BOOL p_bDetBold,
    [in] BOOL p_bDetItalic,
    [in] BOOL p_bDetSize,
    [in] FLOAT p_nDetSizeVal,
    [in] FLOAT p_nDetSizePt,
    [in] BOOL p_bDetColor,
    [in] LONG p_nDetColor,
    [in] BOOL p_bDispAsBold,
    [in] BOOL p_bDispAsItalic,
    [in] LONG p_nDispColor,
    [out] SHORT* p_nDefinition,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nHeading
[in] heading index where to add the definition
p_bEnabled
[in] definition is enabled
p_bDetFont
[in] detect font
p_wsDetFont
[in] font name

```

p_bDetStyle
    [in] detect font style
p_bDetBold
    [in] bold font
p_bDetItalic
    [in] italic font
p_bDetSize
    [in] detect font size
p_nDetSizeVal
    [in] font size
p_nDetSizePt
    [in] font size rounding
p_bDetColor
    [in] detect font color
p_nDetColor
    [in] font color (RGB value)
p_bDispAsBold
    [in] display bookmark font bold
p_bDispAsItalic
    [in] display bookmark font italic
p_nDispColor
    [in] display bookmark font color
p_nDefinition
    [out] definition index, if added. If the definition was not added, -1
p_wsProfileName
    [in] pointer to a null terminated Unicode string containing the profile to modify
p_bPublicProfile
    [in] Flag if the profile is a public or a private profile.

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

```

Remarks:

If you want to define a new heading, pass next heading index in the p_nHeading parameter. There can be defined maximum 9 headings and each of them can contain maximum 9 definitions.

2.3.7.4.57 AddBookmarkDefinition2

The **AddBookmarkDefinition2** method adds a new bookmark definition, having the characteristics specified by the method parameters.

```

HRESULT AddBookmarkDefinition2(
    [in] SHORT p_nHeading,
    [in] BOOL p_bEnabled,
    [in] BOOL p_bDetFont,
    [in, string] BSTR p_wsDetFont,
    [in] BOOL p_bDetStyle,
    [in] BOOL p_bDetBold,
    [in] BOOL p_bDetItalic,
    [in] BOOL p_bDetSize,
    [in] FLOAT p_nDetSizeVal,
    [in] FLOAT p_nDetSizePt,
    [in] BOOL p_bDetColor,
    [in] LONG p_nDetColor,
    [in] BOOL p_bDispAsBold,
    [in] BOOL p_bDispAsItalic,
    [in] LONG p_nDispColor,

```



```

    [out] SHORT* p_nDefinition,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nHeading
 [in] heading index where to add the definition
p_bEnabled
 [in] definition is enabled
p_bDetFont
 [in] detect font flag
p_wsDetFont
 [in] font name
p_bDetStyle
 [in] detect font style
p_bDetBold
 [in] bold font
p_bDetItalic
 [in] italic font
p_bDetSize
 [in] detect font size
p_nDetSizeVal
 [in] font size
p_nDetSizePt
 [in] font size rounding
p_bDetColor
 [in] detect font color
p_nDetColor
 [in] font color (RGB value)
p_bDispAsBold
 [in] display bookmark font bold
p_bDispAsItalic
 [in] display bookmark font italic
p_nDispColor
 [in] display bookmark font color
p_nDefinition
 [out] definition index, if added. If the definition was not added, -1
p_wsProfileName
 [in] pointer to a BSTR containing the profile to modify. If this parameter is a
p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

If you want to define a new heading, pass next heading index in the p_nHeading parameter.
 There can be defined maximum 9 headings and each of them can contain maximum 9 definitions.

2.3.7.4.58 ModifyBookmarkDefinition

The **ModifyBookmarkDefinition** method modifies an existing bookmark definition, having the characteristics specified by the method parameters.

```

HRESULT ModifyBookmarkDefinition(
    [in] SHORT p_nHeading,

```

```

    [in] SHORT p_nDefinition,
    [in] BOOL p_bEnabled,
    [in] BOOL p_bDetFont,
    [in, string] LPCWSTR p_wsDetFont,
    [in] BOOL p_bDetStyle,
    [in] BOOL p_bDetBold,
    [in] BOOL p_bDetItalic,
    [in] BOOL p_bDetSize,
    [in] FLOAT p_nDetSizeVal,
    [in] FLOAT p_nDetSizePt,
    [in] BOOL p_bDetColor,
    [in] LONG p_nDetColor,
    [in] BOOL p_bDispAsBold,
    [in] BOOL p_bDispAsItalic,
    [in] LONG p_nDispColor,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nHeading
 [in] heading index

p_nDefinition
 [in] definition index

p_bEnabled
 [in] definition is enabled

p_bDetFont
 [in] detect font flag

p_wsDetFont
 [in] font name

p_bDetStyle
 [in] detect font style

p_bDetBold
 [in] bold font

p_bDetItalic
 [in] italic font

p_bDetSize
 [in] detect font size

p_nDetSizeVal
 [in] font size

p_nDetSizePt
 [in] font size rounding

p_bDetColor
 [in] detect font color

p_nDetColor
 [in] font color (RGB value)

p_bDispAsBold
 [in] display bookmark font bold

p_bDispAsItalic
 [in] display bookmark font italic

p_nDispColor
 [in] display bookmark font color

p_wsProfileName
 [in] pointer to a null terminated Unicode string containing the profile to modify

p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code

NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
 NV_INVALID_BOOKMARK_DEF - wrong bookmark definition index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

There can be defined maximum 9 headings and each of them can contain maximum 9 definitions.

2.3.7.4.59 ModifyBookmarkDefinition2

The **ModifyBookmarkDefinition2** method modifies an existing bookmark definition, having the characteristics specified by the method parameters.

```
HRESULT ModifyBookmarkDefinition2(
    [in] SHORT p_nHeading,
    [in] SHORT p_nDefinition,
    [in] BOOL p_bEnabled,
    [in] BOOL p_bDetFont,
    [in, string] BSTR p_wsDetFont,
    [in] BOOL p_bDetStyle,
    [in] BOOL p_bDetBold,
    [in] BOOL p_bDetItalic,
    [in] BOOL p_bDetSize,
    [in] FLOAT p_nDetSizeVal,
    [in] FLOAT p_nDetSizePt,
    [in] BOOL p_bDetColor,
    [in] LONG p_nDetColor,
    [in] BOOL p_bDispAsBold,
    [in] BOOL p_bDispAsItalic,
    [in] LONG p_nDispColor,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nHeading
 [in]heading index
 p_nDefinition
 [in]definition index
 p_bEnabled
 [in]definition is enabled
 p_bDetFont
 [in] detect font flag
 p_wsDetFont
 [in] font name
 p_bDetStyle
 [in] detect font style
 p_bDetBold
 [in] bold font
 p_bDetItalic
 [in] italic font
 p_bDetSize
 [in] detect font size
 p_nDetSizeVal
 [in] font size
 p_nDetSizePt
 [in] font size rounding
 p_bDetColor
 [in] detect font color
 p_nDetColor

```

    [in] font color (RGB value)
    p_bDispAsBold
    [in] display bookmark font bold
    p_bDispAsItalic
    [in] display bookmark font italic
    p_nDispColor
    [in] display bookmark font color
    p_wsProfileName
    [in] pointer to a BSTR containing the profile to modify. If this parameter is a
    p_bPublicProfile
    [in] Flag if the profile is a public or a private profile.

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
NV_INVALID_BOOKMARK_DEF - wrong bookmark definition index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

```

Remarks:

There can be defined maximum 9 headings and each of them can contain maximum 9 definitions.

2.3.7.4.60 DeleteBookmarkDefinition

The **DeleteBookmarkDefinition** method deletes an existing bookmark definition.

```

HRESULT DeleteBookmarkDefinition(
    [in] SHORT p_nHeading,
    [in] SHORT p_nDefinition,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_nHeading
    [in] heading index
p_nDefinition
    [in] definition index
p_wsProfileName
    [in] pointer to a null terminated Unicode string containing the profile to modify
p_bPublicProfile
    [in] Flag if the profile is a public or a private profile.

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
NV_INVALID_BOOKMARK_DEF - wrong bookmark definition index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

```

Remarks:

When you delete a bookmark definition the indexes for the remaining definitions will be recalculated. If you delete the last definition for a heading, the heading will be also deleted. In this case, the remaining heading indexes will be also recalculated.

2.3.7.4.61 DeleteBookmarkDefinition2

The **DeleteBookmarkDefinition2** method deletes an existing bookmark definition.

```

HRESULT DeleteBookmarkDefinition2(
    [in] SHORT p_nHeading,

```

```

    [in] SHORT p_nDefinition,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nHeading
 [in] heading index
p_nDefinition
 [in] definition index
p_wsProfileName
 [in] pointer to a BSTR containing the profile to modify. If this parameter is a
p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
 NV_INVALID_BOOKMARK_DEF - wrong bookmark definition index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

When you delete a bookmark definition the indexes for the remaining definitions will be recalculated. If you delete the last definition for a heading, the heading will be also deleted. In this case, the remaining heading indexes will be also recalculated.

2.3.7.4.62 EnableBookmarkDefinition

The **EnableBookmarkDefinition** method enables or disables an existing bookmark definition.

```

HRESULT EnableBookmarkDefinition(
    [in] SHORT p_nHeading,
    [in] SHORT p_nDefinition,
    [in] BOOL p_bEnable,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nHeading
 [in] heading index
p_nDefinition
 [in] definition index
p_bEnable
 [in] flag, enable or disable definition
p_wsProfileName
 [in] pointer to a null terminated Unicode string containing the profile to modify
p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
 NV_INVALID_BOOKMARK_DEF - wrong bookmark definition index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.63 EnableBookmarkDefinition2

The **EnableBookmarkDefinition2** method enables or disables an existing bookmark definition.

```
HRESULT EnableBookmarkDefinition2(
    [in] SHORT p_nHeading,
    [in] SHORT p_nDefinition,
    [in] BOOL p_bEnable,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nHeading
[in] heading index

p_nDefinition
[in] definition index

p_bEnable
[in] flag, enable or disable definition

p_wsProfileName
[in] pointer to BSTR containing the profile to modify. If this parameter is an

p_bPublicProfile
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code

NV_NOT_INITIALIZED - Initialize was not called

NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index

NV_INVALID_BOOKMARK_DEF - wrong bookmark definition index

NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.64 GetBookmarkDefinition

The **GetBookmarkDefinition** method retrieves an existing bookmark definition properties.

```
HRESULT GetBookmarkDefinition(
    [in] SHORT p_nHeading,
    [in] SHORT p_nDefinition,
    [out] BOOL* p_pbEnabled,
    [out] BOOL* p_bDetFont,
    [out, string] LPCWSTR* p_pwsDetFont,
    [out] BOOL* p_pbDetStyle,
    [out] BOOL* p_pbDetBold,
    [out] BOOL* p_pbDetItalic,
    [out] BOOL* p_pbDetSize,
    [out] FLOAT* p_pnDetSizeVal,
    [out] FLOAT* p_pnDetSizePt,
    [out] BOOL* p_pbDetColor,
    [out] LONG* p_pnDetColor,
    [out] BOOL* p_pbDispAsBold,
    [out] BOOL* p_pbDispAsItalic,
    [out] LONG* p_pnDispColor,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nHeading
[in] heading index

p_nDefinition
[in] definition index

```

p_pbEnabled
    [out] definition is enabled
p_pbDetFont
    [out] detect font flag
p_pwsDetFont
    [out] font name
p_pbDetStyle
    [out] detect font style
p_pbDetBold
    [out] bold font
p_pbDetItalic
    [out] italic font
p_pbDetSize
    [out] detect font size
p_pnDetSizeVal
    [out] font size
p_pnDetSizePt
    [out] font size rounding
p_pbDetColor
    [out] detect font color
p_pnDetColor
    [out] font color (RGB value)
p_pbDispAsBold
    [out] display bookmark font bold
p_pbDispAsItalic
    [out] display bookmark font italic
p_pnDispColor
    [out] display bookmark font color
p_wsProfileName
    [in] pointer to a null terminated Unicode string containing the profile to modify
p_bPublicProfile
    [in] Flag if the profile is a public or a private profile.

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
NV_INVALID_BOOKMARK_DEF - wrong bookmark definition index

```

Remarks:

There can be defined maximum 9 headings and each of them can contain maximum 9 definitions.

2.3.7.4.65 GetBookmarkDefinition2

The **GetBookmarkDefinition2** method retrieves an existing bookmark definition properties.

```

HRESULT GetBookmarkDefinition2(
    [in] SHORT p_nHeading,
    [in] SHORT p_nDefinition,
    [out] BOOL* p_pbEnabled,
    [out] BOOL* p_bDetFont,
    [out, string] BSTR* p_pwsDetFont,
    [out] BOOL* p_pbDetStyle,
    [out] BOOL* p_pbDetBold,
    [out] BOOL* p_pbDetItalic,
    [out] BOOL* p_pbDetSize,
    [out] FLOAT* p_pnDetSizeVal,
    [out] FLOAT* p_pnDetSizePt,
    [out] BOOL* p_pbDetColor,
    [out] LONG* p_pnDetColor,

```

```

    [out] BOOL* p_pbDispAsBold,
    [out] BOOL* p_pbDispAsItalic,
    [out] LONG* p_pnDispColor,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nHeading
 [in] heading index
p_nDefinition
 [in] definition index
p_pbEnabled
 [out] definition is enabled
p_pbDetFont
 [out] detect font flag
p_pwsDetFont
 [out] font name
p_pbDetStyle
 [out] detect font style
p_pbDetBold
 [out] bold font
p_pbDetItalic
 [out] italic font
p_pbDetSize
 [out] detect font size
p_pnDetSizeVal
 [out] font size
p_pnDetSizePt
 [out] font size rounding
p_pbDetColor
 [out] detect font color
p_pnDetColor
 [out] font color (RGB value)
p_pbDispAsBold
 [out] display bookmark font bold
p_pbDispAsItalic
 [out] display bookmark font italic
p_pnDispColor
 [out] display bookmark font color
p_wsProfileName
 [in] pointer to a BSTR containing the profile to modify. If this parameter is a
p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index
 NV_INVALID_BOOKMARK_DEF - wrong bookmark definition index

Remarks:

There can be defined maximum 9 headings and each of them can contain maximum 9 definitions.

2.3.7.4.66 GetBookmarkHeaderCount

The **GetBookmarkHeaderCount** method retrieves the number of bookmark headings.
 HRESULT GetBookmarkHeaderCount (


```

    [out] SHORT* p_pnCount,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_pnCount
[out] count of bookmark headings

p_wsProfileName
[in] pointer to a null terminated Unicode string containing the profile to modify

p_bPublicProfile
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called

2.3.7.4.67 GetBookmarkHeaderCount2

The **GetBookmarkHeaderCount2** method retrieves the number of bookmark headings.

```

HRESULT GetBookmarkHeaderCount2(
    [out] SHORT* p_pnCount,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_pnCount
[out] count of bookmark headings

p_wsProfileName
[in] pointer to a BSTR containing the profile to modify. If this parameter is a null string, the profile is the default profile.

p_bPublicProfile
[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called

2.3.7.4.68 GetBookmarkDefinitionCount

The **GetBookmarkDefinitionCount** method retrieves the number of bookmark definitions in a bookmark heading.

```

HRESULT GetBookmarkDefinitionCount(
    [in] SHORT p_nHeading,
    [out] SHORT* p_pnCount,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nHeading
[in] heading index

p_pnCount
[out] count of bookmark headings

p_wsProfileName
[in] pointer to a null terminated Unicode string containing the profile to modify

p_bPublicProfile
[in] Flag if the profile is a public or a private profile.

[in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index

2.3.7.4.69 GetBookmarkDefinitionCount2

The **GetBookmarkDefinitionCount2** method retrieves the number of bookmark definitions in a bookmark heading.

```
HRESULT GetBookmarkDefinitionCount2(
    [in] SHORT p_nHeading,
    [out] SHORT* p_pnCount,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nHeading
 [in] heading index
 p_pnCount
 [out] count of bookmark headings
 p_wsProfileName
 [in] pointer to a BSTR containing the profile to modify. If this parameter is a
 p_bPublicProfile
 [in] Flag if the profile is a public or a private profile.

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_BOOKMARK_HEAD - wrong bookmark header index

2.3.7.4.70 AddWatermarkImage

The **AddWatermarkImage** method adds a new image watermark, having the characteristics specified by the method parameters.

```
HRESULT AddWatermarkImage(
    [in, string] LPCWSTR p_wsName,
    [in, string] LPCWSTR p_wsFile,
    [in] BOOL p_bVisible,
    [in] BOOL p_bFit,
    [in] LONG p_nMarginLeft,
    [in] LONG p_nMarginRight,
    [in] LONG p_nMarginTop,
    [in] LONG p_nMarginBottom,
    [in] BOOL p_bCenterHorizontally,
    [in] BOOL p_bCenterVertically,
    [in] BOOL p_bAlignRightMargin,
    [in] BOOL p_bAlignBottomMargin,
    [in] LONG p_nOriginLeft,
    [in] LONG p_nOriginTop,
    [in] LONG p_nWidth,
    [in] LONG p_nHeight,
    [in] BOOL p_bAspectRatio,
    [in] BOOL p_bUseTranspColor,
    [in] COLORREF p_nTransparentColor,
    [in] SHORT p_nColorVar,
```

```
[in] SHORT p_nRotation,  
[in] WORD p_nOpacity,  
[in] WORD p_nPrintOn,  
[in] BOOL p_bPrintAsBackground,  
[in, string] LPCWSTR p_wsPrintRange,  
[in] WORD p_nPrintPriority,  
[out] SHORT* p_nWatermark,  
[in, string] LPCWSTR p_wsProfileName,  
[in] BOOL p_bPublicProfile  
);
```

Parameters:

```
p_wsName,  
  [in, string] - watermark name  
p_wsFile  
  [in, string] - image file  
p_bVisible  
  [in] - flag if watermark is enabled  
p_bFit  
  [in] - flag, image fit to margins  
p_nMarginLeft  
  [in] - left margin  
p_nMarginRight  
  [in] - right margin  
p_nMarginTop  
  [in] - top margin  
p_nMarginBottom  
  [in] - bottom margin  
p_bCenterHorizontally  
  [in] - flag, image centered horizontally  
p_bCenterVertically  
  [in] - flag, image centered vertically  
p_bAlignRightMargin  
  [in] - flag, align image to right margin  
p_bAlignBottomMargin  
  [in] - flag, align image to bottom margin  
p_nOriginLeft  
  [in] - left origin position  
p_nOriginTop  
  [in] - top origin position  
p_nWidth  
  [in] - image width  
p_nHeight  
  [in] - image height  
p_bAspectRatio  
  [in] - flag, keep image aspect ratio  
p_bUseTransparentColor  
  [in] - flag, use transparent color  
p_nTransparentColor  
  [in] - transparent color  
p_nColorVar  
  [in] - color variation  
p_nRotation  
  [in] - image rotation angle  
p_nOpacity  
  [in] - image opacity  
p_nPrintOn  
  [in] - one of next values:  
    0 - All pages
```

```

    1 - First page
    2 - Even pages
    3 - Odd pages
    4 - Page range
p_bPrintAsBackground
    [in] - flag, print image as background
p_wsPrintRange
    [in] - page range, like "2 - 5"
p_nPrintPriority
    [in] - print priority of the image watermark
p_nWatermark
    [out] - receives the new image watermark index
p_wsProfileName
    [in, string] - pointer to a null terminated Unicode string containing the profile name
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_IMG - wrong image watermark index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

```

2.3.7.4.71 AddWatermarkImage2

The **AddWatermarkImage2** method adds a new image watermark, having the characteristics specified by the method parameters.

```

HRESULT AddWatermarkImage2(
    [in, string] BSTR p_wsName,
    [in, string] BSTR p_wsFile,
    [in] BOOL p_bVisible,
    [in] BOOL p_bFit,
    [in] LONG p_nMarginLeft,
    [in] LONG p_nMarginRight,
    [in] LONG p_nMarginTop,
    [in] LONG p_nMarginBottom,
    [in] BOOL p_bCenterHorizontally,
    [in] BOOL p_bCenterVertically,
    [in] BOOL p_bAlignRightMargin,
    [in] BOOL p_bAlignBottomMargin,
    [in] LONG p_nOriginLeft,
    [in] LONG p_nOriginTop,
    [in] LONG p_nWidth,
    [in] LONG p_nHeight,
    [in] BOOL p_bAspectRatio,
    [in] BOOL p_bUseTranspColor,
    [in] COLORREF p_nTransparentColor,
    [in] SHORT p_nColorVar,
    [in] SHORT p_nRotation,
    [in] WORD p_nOpacity,
    [in] WORD p_nPrintOn,
    [in] BOOL p_bPrintAsBackground,
    [in, string] BSTR p_wsPrintRange,
    [in] WORD p_nPrintPriority,
    [out] SHORT* p_nWatermark,
    [in, string] BSTR p_wsProfileName,

```

```
    [in] BOOL p_bPublicProfile  
);
```

Parameters:

```
p_wsName,  
    [in, string] - watermark name  
p_wsFile  
    [in, string] - image file  
p_bVisible  
    [in] - flag if watermark is enabled  
p_bFit  
    [in] - flag, image fit to margins  
p_nMarginLeft  
    [in] - left margin  
p_nMarginRight  
    [in] - right margin  
p_nMarginTop  
    [in] - top margin  
p_nMarginBottom  
    [in] - bottom margin  
p_bCenterHorizontally  
    [in] - flag, image centered horizontally  
p_bCenterVertically  
    [in] - flag, image centered vertically  
p_bAlignRightMargin  
    [in] - flag, align image to right margin  
p_bAlignBottomMargin  
    [in] - flag, align image to bottom margin  
p_nOriginLeft  
    [in] - left origin position  
p_nOriginTop  
    [in] - top origin position  
p_nWidth  
    [in] - image width  
p_nHeight  
    [in] - image height  
p_bAspectRatio  
    [in] - flag, keep image aspect ratio  
p_bUseTransparentColor  
    [in] - flag, use transparent color  
p_nTransparentColor  
    [in] - transparent color  
p_nColorVar  
    [in] - color variation  
p_nRotation  
    [in] - image rotation angle  
p_nOpacity  
    [in] - image opacity  
p_nPrintOn  
    [in] - one of next values:  
        0 - All pages  
        1 - First page  
        2 - Even pages  
        3 - Odd pages  
        4 - Page range  
p_bPrintAsBackground  
    [in] - flag, print image as background  
p_wsPrintRange  
    [in] - page range, like "2 - 5"
```

```

p_nPrintPriority
    [in] - print priority of the image watermark
p_nWatermark
    [out] - receives the new image watermark index
p_wsProfileName
    [in, string] - pointer to a BSTR containing the profile to modify.
    If this parameter is an empty string, the current active profile is used
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_IMG - wrong image watermark index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

```

2.3.7.4.72 ModifyWatermarkImage

The **ModifyWatermarkImage** method modifies an existing image watermark, having the characteristics specified by the method parameters.

```

HRESULT ModifyWatermarkImage(
    [in] USHORT p_nWatermark,
    [in, string] LPCWSTR p_wsName,
    [in, string] LPCWSTR p_wsFile,
    [in] BOOL p_bVisible,
    [in] BOOL p_bFit,
    [in] LONG p_nMarginLeft,
    [in] LONG p_nMarginRight,
    [in] LONG p_nMarginTop,
    [in] LONG p_nMarginBottom,
    [in] BOOL p_bCenterHorizontally,
    [in] BOOL p_bCenterVertically,
    [in] BOOL p_bAlignRightMargin,
    [in] BOOL p_bAlignBottomMargin,
    [in] LONG p_nOriginLeft,
    [in] LONG p_nOriginTop,
    [in] LONG p_nWidth,
    [in] LONG p_nHeight,
    [in] BOOL p_bAspectRatio,
    [in] BOOL p_bUseTranspColor,
    [in] COLORREF p_nTransparentColor,
    [in] SHORT p_nColorVar,
    [in] SHORT p_nRotation,
    [in] WORD p_nOpacity,
    [in] WORD p_nPrintOn,
    [in] BOOL p_bPrintAsBackground,
    [in, string] LPCWSTR p_wsPrintRange,
    [in] WORD p_nPrintPriority,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_nWatermark,
    [in] - watermark index
p_wsName,
    [in, string] - watermark name
p_wsFile
    [in, string] - image file

```

`p_bVisible`
[in] - flag if watermark is enabled

`p_bFit`
[in] - flag, image fit to margins

`p_nMarginLeft`
[in] - left margin

`p_nMarginRight`
[in] - right margin

`p_nMarginTop`
[in] - top margin

`p_nMarginBottom`
[in] - bottom margin

`p_bCenterHorizontally`
[in] - flag, image centered horizontally

`p_bCenterVertically`
[in] - flag, image centered vertically

`p_bAlignRightMargin`
[in] - flag, align image to right margin

`p_bAlignBottomMargin`
[in] - flag, align image to bottom margin

`p_nOriginLeft`
[in] - left origin position

`p_nOriginTop`
[in] - top origin position

`p_nWidth`
[in] - image width

`p_nHeight`
[in] - image height

`p_bAspectRatio`
[in] - flag, keep image aspect ratio

`p_bUseTransparentColor`
[in] - flag, use transparent color

`p_nTransparentColor`
[in] - transparent color

`p_nColorVar`
[in] - color variation

`p_nRotation`
[in] - image rotation angle

`p_nOpacity`
[in] - image opacity

`p_nPrintOn`
[in] - one of next values:
0 - All pages
1 - First page
2 - Even pages
3 - Odd pages
4 - Page range

`p_bPrintAsBackground`
[in] - flag, print image as background

`p_wsPrintRange`
[in] - page range, like "2 - 5"

`p_nPrintPriority`
[in] - print priority of the image watermark

`p_wsProfileName`
[in, string] - pointer to a null terminated Unicode string containing the profile name
If this parameter is an empty string, the current active profile is used.

`p_bPublicProfile`
[in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_WATERMARK_IMG - wrong image watermark index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.73 ModifyWatermarkImage2

The **ModifyWatermarkImage2** method modifies an existing image watermark, having the characteristics specified by the method parameters.

```
HRESULT ModifyWatermarkImage2(
    [in] USHORT p_nWatermark,
    [in, string] BSTR p_wsName,
    [in, string] BSTR p_wsFile,
    [in] BOOL p_bVisible,
    [in] BOOL p_bFit,
    [in] LONG p_nMarginLeft,
    [in] LONG p_nMarginRight,
    [in] LONG p_nMarginTop,
    [in] LONG p_nMarginBottom,
    [in] BOOL p_bCenterHorizontally,
    [in] BOOL p_bCenterVertically,
    [in] BOOL p_bAlignRightMargin,
    [in] BOOL p_bAlignBottomMargin,
    [in] LONG p_nOriginLeft,
    [in] LONG p_nOriginTop,
    [in] LONG p_nWidth,
    [in] LONG p_nHeight,
    [in] BOOL p_bAspectRatio,
    [in] BOOL p_bUseTranspColor,
    [in] COLORREF p_nTransparentColor,
    [in] SHORT p_nColorVar,
    [in] SHORT p_nRotation,
    [in] WORD p_nOpacity,
    [in] WORD p_nPrintOn,
    [in] BOOL p_bPrintAsBackground,
    [in, string] BSTR p_wsPrintRange,
    [in] WORD p_nPrintPriority,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nWatermark
 [in] - watermark index
 p_wsName
 [in, string] - watermark name
 p_wsFile
 [in, string] - image file
 p_bVisible
 [in] - flag if watermark is enabled
 p_bFit
 [in] - flag, image fit to margins
 p_nMarginLeft
 [in] - left margin
 p_nMarginRight
 [in] - right margin
 p_nMarginTop
 [in] - top margin

`p_nMarginBottom`
[in] - bottom margin

`p_bCenterHorizontally`
[in] - flag, image centered horizontally

`p_bCenterVertically`
[in] - flag, image centered vertically

`p_bAlignRightMargin`
[in] - flag, align image to right margin

`p_bAlignBottomMargin`
[in] - flag, align image to bottom margin

`p_nOriginLeft`
[in] - left origin position

`p_nOriginTop`
[in] - top origin position

`p_nWidth`
[in] - image width

`p_nHeight`
[in] - image height

`p_bAspectRatio`
[in] - flag, keep image aspect ratio

`p_bUseTransparentColor`
[in] - flag, use transparent color

`p_nTransparentColor`
[in] - transparent color

`p_nColorVar`
[in] - color variation

`p_nRotation`
[in] - image rotation angle

`p_nOpacity`
[in] - image opacity

`p_nPrintOn`
[in] - one of next values:
0 - All pages
1 - First page
2 - Even pages
3 - Odd pages
4 - Page range

`p_bPrintAsBackground`
[in] - flag, print image as background

`p_wsPrintRange`
[in] - page range, like "2 - 5"

`p_nPrintPriority`
[in] - print priority of the image watermark

`p_wsProfileName`
[in, string] - pointer to a BSTR containing the profile to modify.
If this parameter is an empty string, the current active profile is used.

`p_bPublicProfile`
[in] - flag, profile is a public profile

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_INVALID_WATERMARK_IMG` - wrong image watermark index
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

2.3.7.4.74 DeleteWatermarkImage

The **DeleteWatermarkImage** method deletes an existing watermark image.

```
HRESULT DeleteWatermarkImage(
    [in] SHORT p_nWatermark,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nWatermark
[in] image watermark index

p_wsProfileName
[in] pointer to a null terminated Unicode string containing the profile to modify

p_bPublicProfile
[in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_WATERMARK_IMG - wrong image watermark index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

When you delete an image watermark, the indexes for the remaining image watermarks will be recalculated.

2.3.7.4.75 DeleteWatermarkImage2

The **DeleteWatermarkImage2** method deletes an existing watermark image.

```
HRESULT DeleteWatermarkImage2(
    [in] SHORT p_nWatermark,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nWatermark
[in] image watermark index

p_wsProfileName
[in] pointer to a BSTR string containing the profile to modify.
If this parameter is an empty string, the current active profile is used.

p_bPublicProfile
[in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_WATERMARK_IMG - wrong image watermark index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

When you delete an image watermark, the indexes for the remaining image watermarks will be recalculated.

2.3.7.4.76 EnableWatermarkImage

The **EnableWatermarkImage** method enables or disables an existing image watermark.

```
HRESULT EnableWatermarkImage(
```

```

    [in] SHORT p_nWatermark,
    [in] BOOL p_bEnable,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nWatermark
[in] image watermark index

p_bEnable
[in] flag, enable or disable definition

p_wsProfileName
[in] pointer to a null terminated Unicode string containing the profile to modify.
If this parameter is an empty string, the current active profile is used.

p_bPublicProfile
[in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_WATERMARK_IMG - wrong image watermark index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.77 EnableWatermarkImage2

The **EnableWatermarkImage2** method enables or disables an existing image watermark.

```

HRESULT EnableWatermarkImage2(
    [in] SHORT p_nWatermark,
    [in] BOOL p_bEnable,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nWatermark
[in] image watermark index

p_bEnable
[in] flag, enable or disable definition

p_wsProfileName
[in] pointer to a BSTR string containing the profile to modify.
If this parameter is an empty string, the current active profile is used.

p_bPublicProfile
[in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_WATERMARK_IMG - wrong image watermark index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.78 GetWatermarkImage

The **GetWatermarkImage** method retrieves an existing image watermark properties.

```

HRESULT GetWatermarkImage(
    [in] SHORT p_nWatermark,
    [out, string] LPWSTR* p_pwsName,
    [out, string] LPWSTR* p_pwsFile,
    [out] BOOL* p_pbVisible,
    [out] BOOL* p_pbFit,
);

```

```

[out] LONG* p_pnMarginLeft,
[out] LONG* p_pnMarginRight,
[out] LONG* p_pnMarginTop,
[out] LONG* p_pnMarginBottom,
[out] BOOL* p_pbCenterHorizontally,
[out] BOOL* p_pbCenterVertically,
[out] BOOL* p_pbAlignRightMargin,
[out] BOOL* p_pbAlignBottomMargin,
[out] LONG* p_pnOriginLeft,
[out] LONG* p_pnOriginTop,
[out] LONG* p_pnWidth,
[out] LONG* p_pnHeight,
[out] BOOL* p_pbAspectRatio,
[out] BOOL* p_pbUseTranspColor,
[out] COLORREF* p_pnTransparentColor,
[out] SHORT* p_pnColorVar,
[out] SHORT* p_pnRotation,
[out] WORD* p_pnOpacity,
[out] WORD* p_pnPrintOn,
[out] BOOL* p_pbPrintAsBackground,
[out, string] LPWSTR* p_pwsPrintRange,
[out] WORD* p_pnPrintPriority,
[in] LPCWSTR p_wsProfileName,
[in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_nWatermark,
[in] - watermark index
p_pwsName,
[out, string] - watermark name
p_pwsFile
[out, string] - image file
p_pbVisible
[out] - flag if watermark is enabled
p_pbFit
[out] - flag, image fit to margins
p_pnMarginLeft
[out] - left margin
p_pnMarginRight
[out] - right margin
p_pnMarginTop
[out] - top margin
p_pnMarginBottom
[out] - bottom margin
p_pbCenterHorizontally
[out] - flag, image centered horizontally
p_pbCenterVertically
[out] - flag, image centered vertically
p_pbAlignRightMargin
[out] - flag, align image to right margin
p_pbAlignBottomMargin
[out] - flag, align image to bottom margin
p_pnOriginLeft
[out] - left origin position
p_pnOriginTop
[out] - top origin position
p_pnWidth
[out] - image width

```

```

p_pnHeight
    [out] - image height
p_pbAspectRatio
    [out] - flag, keep image aspect ratio
p_pbUseTransparentColor
    [out] -flag, use transparent color
p_pnTransparentColor
    [out] - transparent color
p_pnColorVar
    [out] - color variation
p_pnRotation
    [out] - image rotation angle
p_pnOpacity
    [out] - image opacity
p_pnPrintOn
    [out] - one of next values:
        0 - All pages
        1 - First page
        2 - Even pages
        3 - Odd pages
        4 - Page range
p_pbPrintAsBackground
    [out] - flag, print image as background
p_pwsPrintRange
    [out] - page range, like "2 - 5"
p_pnPrintPriority
    [out] - print priority of the image watermark
p_wsProfileName
    [in, string] - pointer to a null terminated Unicode string containing the profile name
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_IMG - wrong image watermark index

```

2.3.7.4.79 GetWatermarkImage2

The **GetWatermarkImage** method retrieves an existing image watermark properties.

```

HRESULT GetWatermarkImage(
    [in] SHORT p_nWatermark,
    [out, string] BSTR* p_pwsName,
    [out, string] BSTR* p_pwsFile,
    [out] BOOL* p_pbVisible,
    [out] BOOL* p_pbFit,
    [out] LONG* p_pnMarginLeft,
    [out] LONG* p_pnMarginRight,
    [out] LONG* p_pnMarginTop,
    [out] LONG* p_pnMarginBottom,
    [out] BOOL* p_pbCenterHorizontally,
    [out] BOOL* p_pbCenterVertically,
    [out] BOOL* p_pbAlignRightMargin,
    [out] BOOL* p_pbAlignBottomMargin,
    [out] LONG* p_pnOriginLeft,
    [out] LONG* p_pnOriginTop,
    [out] LONG* p_pnWidth,

```

```

    [out] LONG* p_pnHeight,
    [out] BOOL* p_pbAspectRatio,
    [out] BOOL* p_pbUseTransparentColor,
    [out] COLORREF* p_pnTransparentColor,
    [out] SHORT* p_pnColorVar,
    [out] SHORT* p_pnRotation,
    [out] WORD* p_pnOpacity,
    [out] WORD* p_pnPrintOn,
    [out] BOOL* p_pbPrintAsBackground,
    [out, string] BSTR* p_pwsPrintRange,
    [out] WORD* p_pnPrintPriority,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_nWatermark,
    [in] - watermark index
p_pwsName,
    [out, string] - watermark name
p_pwsFile
    [out, string] - image file
p_pbVisible
    [out] - flag if watermark is enabled
p_pbFit
    [out] - flag, image fit to margins
p_pnMarginLeft
    [out] - left margin
p_pnMarginRight
    [out] - right margin
p_pnMarginTop
    [out] - top margin
p_pnMarginBottom
    [out] - bottom margin
p_pbCenterHorizontally
    [out] - flag, image centered horizontally
p_pbCenterVertically
    [out] - flag, image centered vertically
p_pbAlignRightMargin
    [out] - flag, align image to right margin
p_pbAlignBottomMargin
    [out] - flag, align image to bottom margin
p_pnOriginLeft
    [out] - left origin position
p_pnOriginTop
    [out] - top origin position
p_pnWidth
    [out] - image width
p_pnHeight
    [out] - image height
p_pbAspectRatio
    [out] - flag, keep image aspect ratio
p_pbUseTransparentColor
    [out] - flag, use transparent color
p_pnTransparentColor
    [out] - transparent color
p_pnColorVar
    [out] - color variation
p_pnRotation

```

```

    [out] - image rotation angle
p_pnOpacity
    [out] - image opacity
p_pnPrintOn
    [out] - one of next values:
        0 - All pages
        1 - First page
        2 - Even pages
        3 - Odd pages
        4 - Page range
p_pbPrintAsBackground
    [out] - flag, print image as background
p_pwsPrintRange
    [out] - page range, like "2 - 5"
p_pnPrintPriority
    [out] - print priority of the image watermark
p_wsProfileName
    [in, string] - pointer to a BSTR string containing the profile to modify.
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_IMG - wrong image watermark index

```

2.3.7.4.80 GetWatermarkImageCount

The **GetWatermarkImageCount** method retrieves the number of image watermarks.

```

HRESULT GetWatermarkImageCount(
    [out] SHORT* p_pnCount,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_pnCount
    [out] count of image watermarks
p_wsProfileName
    [in] pointer to a null terminated Unicode string containing the profile to modify.
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called

```

2.3.7.4.81 GetWatermarkImageCount2

The **GetWatermarkImageCount2** method retrieves the number of bookmark headings.

```

HRESULT GetWatermarkImageCount2(
    [out] SHORT* p_pnCount,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_pnCount
 [out] - count of image watermarks
 p_wsProfileName
 [in] - pointer to a BSTR string containing the profile to modify.
 If this parameter is an empty string, the current active profile is used.
 p_bPublicProfile
 [in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called

2.3.7.4.82 AddWatermarkText

The **AddWatermarkText** method adds a new text watermark, having the characteristics specified by the method parameters.

```

HRESULT AddWatermarkText(
    [in, string] LPCWSTR p_wsName,
    [in, string] LPCWSTR p_wsText,
    [in, string] LPCWSTR p_wsFont,
    [in] LONG p_nFontSize,
    [in] BOOL p_bBold,
    [in] BOOL p_bItalic,
    [in] BOOL p_bOutline,
    [in] COLORREF p_nColor,
    [in] SHORT p_nRotation,
    [in] WORD p_nOpacity,
    [in] BOOL p_bVisible,
    [in] BOOL p_bFit,
    [in] LONG p_nMarginLeft,
    [in] LONG p_nMarginRight,
    [in] LONG p_nMarginTop,
    [in] LONG p_nMarginBottom,
    [in] BOOL p_bCenterHorizontally,
    [in] BOOL p_bCenterVertically,
    [in] BOOL p_bAlignRightMargin,
    [in] BOOL p_bAlignBottomMargin,
    [in] LONG p_nOriginLeft,
    [in] LONG p_nOriginTop,
    [in] WORD p_nPrintOn,
    [in] BOOL p_bPrintAsBackground,
    [in, string] LPCWSTR p_wsPrintRange,
    [in] WORD p_nPrintPriority,
    [out] SHORT* p_nWatermark,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
  
```

Parameters:

p_wsName,
 [in, string] - watermark name
 p_wsText
 [in, string] - watermark text
 p_wsFont
 [in, string] - font name
 p_bBold
 [in] - flag, font is bold
 p_bItalic
 [in] - flag, font is italic

`p_bOutline`
[in] - flag, font is outline

`p_nColor`
[in] - font color

`p_nRotation`
[in] - text rotation angle

`p_nOpacity`
[in] - text color opacity

`p_bVisible`
[in] - flag if watermark is enabled

`p_bFit`
[in] - flag, image fit to margins

`p_nMarginLeft`
[in] - left margin

`p_nMarginRight`
[in] - right margin

`p_nMarginTop`
[in] - top margin

`p_nMarginBottom`
[in] - bottom margin

`p_bCenterHorizontally`
[in] - flag, image centered horizontally

`p_bCenterVertically`
[in] - flag, image centered vertically

`p_bAlignRightMargin`
[in] - flag, align image to right margin

`p_bAlignBottomMargin`
[in] - flag, align image to bottom margin

`p_nOriginLeft`
[in] - left origin position

`p_nOriginTop`
[in] - top origin position

`p_nPrintOn`
[in] - one of next values:
0 - All pages
1 - First page
2 - Even pages
3 - Odd pages
4 - Page range

`p_bPrintAsBackground`
[in] - flag, print image as background

`p_wsPrintRange`
[in] - page range, like "2 - 5"

`p_nPrintPriority`
[in] - print priority of the image watermark

`p_nWatermark`
[out] - receives the new image watermark index

`p_wsProfileName`
[in, string] - pointer to a null terminated Unicode string containing the profile name
If this parameter is an empty string, the current active profile is used.

`p_bPublicProfile`
[in] - flag, profile is a public profile

Return values:

`S_OK` on success or COM error code
`NV_NOT_INITIALIZED` - Initialize was not called
`NV_INVALID_WATERMARK_TXT` - wrong text watermark index
`NV_PUBLIC_PROFILE` - you cannot change public profiles only on server

2.3.7.4.83 AddWatermarkText2

The **AddWatermarkText2** method adds a new text watermark, having the characteristics specified by the method parameters.

```

HRESULT AddWatermarkText2(
    [in, string] BSTR p_wsName,
    [in, string] BSTR p_wsText,
    [in, string] BSTR p_wsFont,
    [in] LONG p_nFontSize,
    [in] BOOL p_bBold,
    [in] BOOL p_bItalic,
    [in] BOOL p_bOutline,
    [in] COLORREF p_nColor,
    [in] SHORT p_nRotation,
    [in] WORD p_nOpacity,
    [in] BOOL p_bVisible,
    [in] BOOL p_bFit,
    [in] LONG p_nMarginLeft,
    [in] LONG p_nMarginRight,
    [in] LONG p_nMarginTop,
    [in] LONG p_nMarginBottom,
    [in] BOOL p_bCenterHorizontally,
    [in] BOOL p_bCenterVertically,
    [in] BOOL p_bAlignRightMargin,
    [in] BOOL p_bAlignBottomMargin,
    [in] LONG p_nOriginLeft,
    [in] LONG p_nOriginTop,
    [in] WORD p_nPrintOn,
    [in] BOOL p_bPrintAsBackground,
    [in, string] BSTR p_wsPrintRange,
    [in] WORD p_nPrintPriority,
    [out] SHORT* p_nWatermark,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_wsName,
    [in, string] - watermark name
p_wsText
    [in, string] - watermark text
p_wsFont
    [in, string] - font name
p_bBold
    [in] - flag, font is bold
p_bItalic
    [in] - flag, font is italic
p_bOutline
    [in] - flag, font is outline
p_nColor
    [in] - font color
p_nRotation
    [in] - text rotation angle
p_nOpacity
    [in] - text color opacity
p_bVisible
    [in] - flag if watermark is enabled
p_bFit
    [in] - flag, image fit to margins

```

```

p_nMarginLeft
    [in] - left margin
p_nMarginRight
    [in] - right margin
p_nMarginTop
    [in] - top margin
p_nMarginBottom
    [in] - bottom margin
p_bCenterHorizontally
    [in] - flag, image centered horizontally
p_bCenterVertically
    [in] - flag, image centered vertically
p_bAlignRightMargin
    [in] - flag, align image to right margin
p_bAlignBottomMargin
    [in] - flag, align image to bottom margin
p_nOriginLeft
    [in] - left origin position
p_nOriginTop
    [in] - top origin position
p_nPrintOn
    [in] - one of next values:
        0 - All pages
        1 - First page
        2 - Even pages
        3 - Odd pages
        4 - Page range
p_bPrintAsBackground
    [in] - flag, print image as background
p_wsPrintRange
    [in] - page range, like "2 - 5"
p_nPrintPriority
    [in] - print priority of the image watermark
p_nWatermark
    [out] - receives the new image watermark index
p_wsProfileName
    [in, string] - pointer to a null terminated Unicode string containing the profile name
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_TXT - wrong text watermark index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

```

2.3.7.4.84 ModifyWatermarkText

The **ModifyWatermarkText** method modifies an existing text watermark, having the characteristics specified by the method parameters.

```

HRESULT ModifyWatermarkText(
    [in] USHORT p_nWatermark,
    [in, string] LPCWSTR p_wsName,
    [in, string] LPCWSTR p_wsText,
    [in, string] LPCWSTR p_wsFont,
    [in] LONG p_nFontSize,
    [in] BOOL p_bBold,
    [in] BOOL p_bItalic,

```

```

[in] BOOL p_bOutline,
[in] COLORREF p_nColor,
[in] SHORT p_nRotation,
[in] WORD p_nOpacity,
[in] BOOL p_bVisible,
[in] BOOL p_bFit,
[in] LONG p_nMarginLeft,
[in] LONG p_nMarginRight,
[in] LONG p_nMarginTop,
[in] LONG p_nMarginBottom,
[in] BOOL p_bCenterHorizontally,
[in] BOOL p_bCenterVertically,
[in] BOOL p_bAlignRightMargin,
[in] BOOL p_bAlignBottomMargin,
[in] LONG p_nOriginLeft,
[in] LONG p_nOriginTop,
[in] WORD p_nPrintOn,
[in] BOOL p_bPrintAsBackground,
[in, string] LPCWSTR p_wsPrintRange,
[in] WORD p_nPrintPriority,
[in, string] LPCWSTR p_wsProfileName,
[in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_nWatermark,
[in] - watermark index
p_wsName,
[in, string] - watermark name
p_wsText
[in, string] - watermark text
p_wsFont
[in, string] - font name
p_bBold
[in] - flag, font is bold
p_bItalic
[in] - flag, font is italic
p_bOutline
[in] - flag, font is outline
p_nColor
[in] - font color
p_nRotation
[in] - text rotation angle
p_nOpacity
[in] - text color opacity
p_bVisible
[in] - flag if watermark is enabled
p_bFit
[in] - flag, image fit to margins
p_nMarginLeft
[in] - left margin
p_nMarginRight
[in] - right margin
p_nMarginTop
[in] - top margin
p_nMarginBottom
[in] - bottom margin
p_bCenterHorizontally
[in] - flag, image centered horizontally

```

```

p_bCenterVertically
    [in] - flag, image centered vertically
p_bAlignRightMargin
    [in] - flag, align image to right margin
p_bAlignBottomMargin
    [in] - flag, align image to bottom margin
p_nOriginLeft
    [in] - left origin position
p_nOriginTop
    [in] - top origin position
p_nPrintOn
    [in] - one of next values:
        0 - All pages
        1 - First page
        2 - Even pages
        3 - Odd pages
        4 - Page range
p_bPrintAsBackground
    [in] - flag, print image as background
p_wsPrintRange
    [in] - page range, like "2 - 5"
p_nPrintPriority
    [in] - print priority of the image watermark
p_nWatermark
    [out] - receives the new image watermark index
p_wsProfileName
    [in, string] - pointer to a null terminated Unicode string containing the profile name
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_TXT - wrong text watermark index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

```

2.3.7.4.85 ModifyWatermarkText2

The **ModifyWatermarkText2** method modifies an existing text watermark, having the characteristics specified by the method parameters.

```

HRESULT ModifyWatermarkText2(
    [in] USHORT p_nWatermark,
    [in, string] BSTR p_wsName,
    [in, string] BSTR p_wsText,
    [in, string] BSTR p_wsFont,
    [in] LONG p_nFontSize,
    [in] BOOL p_bBold,
    [in] BOOL p_bItalic,
    [in] BOOL p_bOutline,
    [in] COLORREF p_nColor,
    [in] SHORT p_nRotation,
    [in] WORD p_nOpacity,
    [in] BOOL p_bVisible,
    [in] BOOL p_bFit,
    [in] LONG p_nMarginLeft,
    [in] LONG p_nMarginRight,
    [in] LONG p_nMarginTop,

```

```

[in] LONG p_nMarginBottom,
[in] BOOL p_bCenterHorizontally,
[in] BOOL p_bCenterVertically,
[in] BOOL p_bAlignRightMargin,
[in] BOOL p_bAlignBottomMargin,
[in] LONG p_nOriginLeft,
[in] LONG p_nOriginTop,
[in] WORD p_nPrintOn,
[in] BOOL p_bPrintAsBackground,
[in, string] BSTR p_wsPrintRange,
[in] WORD p_nPrintPriority,
[in, string] BSTR p_wsProfileName,
[in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_nWatermark,
[in] - watermark index
p_wsName,
[in, string] - watermark name
p_wsText
[in, string] - watermark text
p_wsFont
[in, string] - font name
p_bBold
[in] - flag, font is bold
p_bItalic
[in] - flag, font is italic
p_bOutline
[in] - flag, font is outline
p_nColor
[in] - font color
p_nRotation
[in] - text rotation angle
p_nOpacity
[in] - text color opacity
p_bVisible
[in] - flag if watermark is enabled
p_bFit
[in] - flag, image fit to margins
p_nMarginLeft
[in] - left margin
p_nMarginRight
[in] - right margin
p_nMarginTop
[in] - top margin
p_nMarginBottom
[in] - bottom margin
p_bCenterHorizontally
[in] - flag, image centered horizontally
p_bCenterVertically
[in] - flag, image centered vertically
p_bAlignRightMargin
[in] - flag, align image to right margin
p_bAlignBottomMargin
[in] - flag, align image to bottom margin
p_nOriginLeft
[in] - left origin position
p_nOriginTop

```

[in] - top origin position
 p_nPrintOn
 [in] - one of next values:
 0 - All pages
 1 - First page
 2 - Even pages
 3 - Odd pages
 4 - Page range
 p_bPrintAsBackground
 [in] - flag, print image as background
 p_wsPrintRange
 [in] - page range, like "2 - 5"
 p_nPrintPriority
 [in] - print priority of the image watermark
 p_nWatermark
 [out] - receives the new image watermark index
 p_wsProfileName
 [in, string] - pointer to a null terminated Unicode string containing the profile name
 If this parameter is an empty string, the current active profile is used.
 p_bPublicProfile
 [in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_WATERMARK_TXT - wrong text watermark index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.86 DeleteWatermarkText

The **DeleteWatermarkText** method deletes an existing text watermark.

```
HRESULT DeleteWatermarkText(
    [in] SHORT p_nWatermark,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nWatermark
 [in] image watermark index
 p_wsProfileName
 [in] pointer to a null terminated Unicode string containing the profile to modify
 p_bPublicProfile
 [in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_WATERMARK_TXT - wrong image watermark index
 NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

When you delete a text watermark, the indexes for the remaining text watermarks will be recalculated.

2.3.7.4.87 DeleteWatermarkText2

The **DeleteWatermarkText2** method deletes an existing text watermark.

```
HRESULT DeleteWatermarkText2(
```

```

    [in] SHORT p_nWatermark,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nWatermark
[in] image watermark index

p_wsProfileName
[in] pointer to a null terminated Unicode string containing the profile to modify. If this parameter is an empty string, the current active profile is used.

p_bPublicProfile
[in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_TXT - wrong image watermark index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

Remarks:

When you delete a text watermark, the indexes for the remaining text watermarks will be recalculated.

2.3.7.4.88 EnableWatermarkText

The **EnableWatermarkText** method enables or disables an existing text watermark.

```

HRESULT EnableWatermarkText(
    [in] SHORT p_nWatermark,
    [in] BOOL p_bEnable,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

p_nWatermark
[in] image watermark index

p_bEnable
[in] flag, enable or disable definition

p_wsProfileName
[in] pointer to a null terminated Unicode string containing the profile to modify. If this parameter is an empty string, the current active profile is used.

p_bPublicProfile
[in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_TXT - wrong image watermark index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

2.3.7.4.89 EnableWatermarkText2

The **EnableWatermarkText2** method enables or disables an existing text watermark.

```

HRESULT EnableWatermarkText2(
    [in] SHORT p_nWatermark,
    [in] BOOL p_bEnable,
    [in, string] BSTR p_wsProfileName,

```



```

    [in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_nWatermark
    [in] image watermark index
p_bEnable
    [in] flag, enable or disable definition
p_wsProfileName
    [in] pointer to a null terminated Unicode string containing the profile to modify.
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_TXT - wrong image watermark index
NV_PUBLIC_PROFILE - you cannot change public profiles only on server

```

2.3.7.4.90 GetWatermarkText

The **GetWatermarkText** method retrieves an existing text watermark properties.

```

HRESULT GetWatermarkText(
    [in] SHORT p_nWatermark,
    [out, string] LPWSTR* p_pwsName,
    [out, string] LPWSTR* p_pwsText,
    [out, string] LPWSTR* p_pwsFont,
    [out] LONG* p_pnFontSize,
    [out] BOOL* p_pbBold,
    [out] BOOL* p_pbItalic,
    [out] BOOL* p_pbOutline,
    [out] COLORREF* p_pnColor,
    [out] SHORT* p_pnRotation,
    [out] WORD* p_pnOpacity,
    [out] BOOL* p_pbVisible,
    [out] BOOL* p_pbFit,
    [out] LONG* p_pnMarginLeft,
    [out] LONG* p_pnMarginRight,
    [out] LONG* p_pnMarginTop,
    [out] LONG* p_pnMarginBottom,
    [out] BOOL* p_pbCenterHorizontally,
    [out] BOOL* p_pbCenterVertically,
    [out] BOOL* p_pbAlignRightMargin,
    [out] BOOL* p_pbAlignBottomMargin,
    [out] LONG* p_pnOriginLeft,
    [out] LONG* p_pnOriginTop,
    [out] WORD* p_pnPrintOn,
    [out] BOOL* p_pbPrintAsBackground,
    [out, string] LPWSTR* p_pwsPrintRange,
    [out] WORD* p_pnPrintPriority,
    [in] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);

```

Parameters:

```

p_nWatermark,
    [in] - text watermark index

```

```
p_pwsName,
    [out, string] - watermark name
p_pwsText
    [out, string] - watermark text
p_pwsFont
    [out, string] - font name
p_pbBold
    [out] - flag, font is bold
p_pbItalic
    [out] - flag, font is italic
p_pbOutline
    [out] - flag, font is outline
p_pnColor
    [out] - font color
p_pnRotation
    [out] - text rotation angle
p_pnOpacity
    [out] - text color opacity
p_pbVisible
    [out] - flag if watermark is enabled
p_pbFit
    [out] - flag, image fit to margins
p_pnMarginLeft
    [out] - left margin
p_pnMarginRight
    [out] - right margin
p_pnMarginTop
    [out] - top margin
p_pnMarginBottom
    [out] - bottom margin
p_pbCenterHorizontally
    [out] - flag, image centered horizontally
p_pbCenterVertically
    [out] - flag, image centered vertically
p_pbAlignRightMargin
    [out] - flag, align image to right margin
p_pbAlignBottomMargin
    [out] - flag, align image to bottom margin
p_pnOriginLeft
    [out] - left origin position
p_pnOriginTop
    [out] - top origin position
p_pnPrintOn
    [out] - one of next values:
        0 - All pages
        1 - First page
        2 - Even pages
        3 - Odd pages
        4 - Page range
p_pbPrintAsBackground
    [out] - flag, print image as background
p_pwsPrintRange
    [out] - page range, like "2 - 5"
p_pnPrintPriority
    [out] - print priority of the image watermark
p_wsProfileName
    [in, string] - pointer to a null terminated Unicode string containing the profile name
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
```

[in] - flag, profile is a public profile

Return values:

S_OK on success or COM error code
 NV_NOT_INITIALIZED - Initialize was not called
 NV_INVALID_WATERMARK_TXT - wrong text watermark index

2.3.7.4.91 GetWatermarkText2

The **GetWatermarkText2** method retrieves an existing text watermark properties.

```
HRESULT GetWatermarkText2(
    [in] SHORT p_nWatermark,
    [out, string] BSTR* p_pwsName,
    [out, string] BSTR* p_pwsText,
    [out, string] BSTR* p_pwsFont,
    [out] LONG* p_pnFontSize,
    [out] BOOL* p_pbBold,
    [out] BOOL* p_pbItalic,
    [out] BOOL* p_pbOutline,
    [out] COLORREF* p_pnColor,
    [out] SHORT* p_pnRotation,
    [out] WORD* p_pnOpacity,
    [out] BOOL* p_pbVisible,
    [out] BOOL* p_pbFit,
    [out] LONG* p_pnMarginLeft,
    [out] LONG* p_pnMarginRight,
    [out] LONG* p_pnMarginTop,
    [out] LONG* p_pnMarginBottom,
    [out] BOOL* p_pbCenterHorizontally,
    [out] BOOL* p_pbCenterVertically,
    [out] BOOL* p_pbAlignRightMargin,
    [out] BOOL* p_pbAlignBottomMargin,
    [out] LONG* p_pnOriginLeft,
    [out] LONG* p_pnOriginTop,
    [out] WORD* p_pnPrintOn,
    [out] BOOL* p_pbPrintAsBackground,
    [out, string] BSTR* p_pwsPrintRange,
    [out] WORD* p_pnPrintPriority,
    [in] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

p_nWatermark
 [in] - text watermark index
 p_pwsName
 [out, string] - watermark name
 p_pwsText
 [out, string] - watermark text
 p_pwsFont
 [out, string] - font name
 p_pbBold
 [out] - flag, font is bold
 p_pbItalic
 [out] - flag, font is italic
 p_pbOutline
 [out] - flag, font is outline
 p_pnColor
 [out] - font color

```

p_pnRotation
    [out] - text rotation angle
p_pnOpacity
    [out] - text color opacity
p_pbVisible
    [out] - flag if watermark is enabled
p_pbFit
    [out] - flag, image fit to margins
p_pnMarginLeft
    [out] - left margin
p_pnMarginRight
    [out] - right margin
p_pnMarginTop
    [out] - top margin
p_pnMarginBottom
    [out] - bottom margin
p_pbCenterHorizontally
    [out] - flag, image centered horizontally
p_pbCenterVertically
    [out] - flag, image centered vertically
p_pbAlignRightMargin
    [out] - flag, align image to right margin
p_pbAlignBottomMargin
    [out] - flag, align image to bottom margin
p_pnOriginLeft
    [out] - left origin position
p_pnOriginTop
    [out] - top origin position
p_pnPrintOn
    [out] - one of next values:
        0 - All pages
        1 - First page
        2 - Even pages
        3 - Odd pages
        4 - Page range
p_pbPrintAsBackground
    [out] - flag, print image as background
p_pwsPrintRange
    [out] - page range, like "2 - 5"
p_pnPrintPriority
    [out] - print priority of the image watermark
p_wsProfileName
    [in, string] - pointer to a null terminated Unicode string containing the profile name
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile

```

Return values:

```

S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
NV_INVALID_WATERMARK_TXT - wrong text watermark index

```

2.3.7.4.92 GetWatermarkTextCount

The **GetWatermarkTextCount** method retrieves the number of text watermarks.

```

HRESULT GetWatermarkTextCount(
    [out] SHORT* p_pnCount,
    [in, string] LPCWSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile

```

```
);
```

Parameters:

```
p_pnCount
    [out] count of text watermarks
p_wsProfileName
    [in] pointer to a null terminated Unicode string containing the profile to modify
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile
```

Return values:

```
S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
```

2.3.7.4.93 GetWatermarkTextCount2

The **GetWatermarkTextCount2** method retrieves the number of text watermarks.

```
HRESULT GetWatermarkTextCount2(
    [out] SHORT* p_pnCount,
    [in, string] BSTR p_wsProfileName,
    [in] BOOL p_bPublicProfile
);
```

Parameters:

```
p_pnCount
    [out] count of text watermarks
p_wsProfileName
    [in] pointer to a null terminated Unicode string containing the profile to modify
    If this parameter is an empty string, the current active profile is used.
p_bPublicProfile
    [in] - flag, profile is a public profile
```

Return values:

```
S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
```

2.3.7.4.94 GetPDFFileName

The **GetPDFFileName** method retrieves the name of the last generated PDF file.

```
HRESULT GetPDFFileName(
    [in] BOOL p_bPrintStarted,
    [out, string] LPWSTR* p_pwsFileName
);
```

Parameters:

```
p_bPrintStarted
    [in] flag, what file name to retrieve. See Remarks.
p_pwsFileName
    [out] pointer to a pointer to a null terminated Unicode string that will contain the file name.
    On success this value must be freed by the caller with CoTaskMemFree.
```

Return values:

```
S_OK on success or COM error code
NV_NOT_INITIALIZED - Initialize was not called
```

Remarks:

Because the novaPDF printer works with the printer spooler queue, the documents sent to the printer are added to the queue. If there are already some other documents in the queue, the

current document is not processed until the previous ones are finished.

There are two PDF file names you can find out, depending on the value of the `p_bPrintStarted` flag:

- the name of the PDF file that was just sent to the printer
- the name of the PDF file that is currently processed by the printer

This information is available only on the computer that starts the print job, if the PDF file is saved local and not on the network.

2.4 Samples

2.4.1 What sample to choose

There are several modes to start a print job to novaPDF printer, and depending on your application, you should choose a different sample:

1. If you perform a print job by calling other controls "Print()" method, or if you print an existing document using "ShellExecute()" function, you should check the MFC Converter sample.
2. If you create a printer job using Windows API calls like `OpenPrinter`, `StartDoc`,.... you should check the Hello World sample.
3. If your application runs on a network check the Hello World (network) sample.
4. If you have a document/view MFC architecture check the MFC Scribble sample.
5. If you have a Delphi application and you print using the Printer object provided by Delphi, check the Hello World Delphi sample.
6. If you have a Delphi application and you print using "ShellExecute()" or you want to handle printing events, check the VCLConverter sample.
7. If you have a C# application that prints using the package "System.Drawing.Printing", check the Hello World CSharp sample.
8. If you have a C# application and intend to convert existing files to PDF, see the CSharp Converter sample.
9. If you have a VB application and you print using the Printer object provided by VB, check the Hello World VB sample.
10. If you have a VB application and you print using "ShellExecute()" or you want to handle printing events, check the VB Converter sample.
11. If you have a VBNet application that prints using the package "System.Drawing.Printing", check the Hello World VBNet sample.
12. If you have a VBNet application that prints using the package "System.Drawing.Printing", check the VBNet Converter sample.
13. If you have an Access database and you want to generate PDF files, check the PDF Reports Access sample.
14. If you want to convert MS Word documents or if you use other OLE controls to print your

documents, choose one of the next samples: Word OLE CSharp, Word OLE Delphi, Word OLE VB or Word OLE VBNet.

2.4.2 Access

2.4.2.1 PDF Reports

PDF Reports Sample is an Access database with one table and one form. On the form you can set several options for the novaPDF Printer and then press a button to generate a PDF file. A report is made on the table and it is sent to novaPDF Printer.

It demonstrates the basic use of the INovaPDFOptions interface. The printing job is made using the object "Application.Printer"

Basically the sample creates a new profile called "Access Profile", sets the new profile as active, sets the user options from form controls, opens and prints a report, and restores original printer settings.

Source code

```
Option Compare Database
Option Explicit

Private objPDF As Object

Const strIAPProfile As String = "Access Profile"
Const strPDFDriver As String = "novaPDF Pro v5"
Const bIAPublicProfile As Long = 0

Private Sub cmdCreatePDF_Click()
    On Error GoTo Error_cmdCreatePDF_Click

    Dim strActiveProfile As String
    Dim strDefaultPrinter As String
    Dim nActiveProfilePublic As Long

    ' create the NovaPdfOptions object
    Set objPDF = CreateObject("novapi.NovaPdfOptions")

    ' initialize the NovaPdfOptions object
    ' if you have an application license for novaPDF SDK,
    ' pass both the registration name and the license key to the Initialize() function
    ' pNova.Initialize2 strPDFDriver, '<registration name>', '<license key>'
    objPDF.Initialize2 strPDFDriver, "", "", ""

    ' Store the Default Printer. * Note - Access cannot use the objPDF.SetDefaultPrinter
    ' doesn't update Access internally fast enough. You must use the Application.Printer
    strDefaultPrinter = Application.Printer.DeviceName

    ' Get the Active Profile
    objPDF.GetActiveProfile2 strActiveProfile, nActiveProfilePublic

    ' Add new profile
    objPDF.AddProfile2 strIAPProfile, bIAPublicProfile

    With Me
        ' *****
        ' Set save options
    End With
End Sub
```

```

objPDF.SetOptionLong2 PDF_SAVE_PROMPT, !optSaveOptions, strIAProfile, bIAP
objPDF.SetOptionString2 PDF_SAVE_FOLDER, !txtSaveFolder, strIAProfile, bIAP
objPDF.SetOptionString2 PDF_SAVE_FILE, !txtFilename, strIAProfile, bIAPubl
objPDF.SetOptionLong2 PDF_SAVE_CONFLICT_STRATEGY, !cboWhenFileExists, strI

' After Save Action
objPDF.SetOptionLong2 PDF_ACTION_Open_DOCUMENT, !chkOpenViewer, strIAProfi
objPDF.SetOptionLong2 PDF_ACTION_USE_DEFAULT_VIEWER, !chkOpenViewer, strIA

' .... other options

' Set the PDF print driver.
objPDF.SetActiveProfile2 strIAProfile, bIAPublicProfile

' Set the Default printer.
Set Application.Printer = Application.Printers(strPDFDriver)

' Run the selected report and create a PDF file.
DoCmd.OpenReport "rptSMZipCode"

' Return to previous settings
objPDF.SetActiveProfile2 strActiveProfile, nActiveProfilePublic
objPDF.DeleteProfile2 strIAProfile, bIAPublicProfile

' Restore the Default Printer.
Set Application.Printer = Application.Printers(strDefaultPrinter)
End With

Exit_cmdCreatePDF_Click:
Set objPDF = Nothing
Exit Sub
Error_cmdCreatePDF_Click:
Debug.Print Err.Number & ":" & Err.Description
Resume Next
End Sub

```

2.4.3 Delphi

2.4.3.1 VCL Converter

The **VCL Converter** sample demonstrates how to convert an existing file by printing it to novaPDF Printer using the ShellExecute function. It also demonstrates how to set different options and manage profiles.

The same approach should be taken if you print using a "Print()" method from another object (like an internet browser or a report control). Just replace the ShellExecute call with the call of your Print method.

When the application starts, it creates a few profiles and makes different settings in the profiles. Then it shows a dialog from where the user can select the active profile and change its settings using the controls from the dialog.

After that a document can be selected from the harddisk and printed to novaPDF Printer using the ShellExecute function call.

When using this technique to convert a file to PDF, you have to take care of the fact that ShellExecute prints to the default printer. This function returns immediately and does not wait until the print is finished (it may return before the printing is actually started). Therefore you have

to set the default printer to novaPDF Printer before calling ShellExecute (using the SetDefaultPrinter method), register FileSaved message (or any other novaPDF Printer message) to be sure that the print job was started. In this message handler restore the default printer (with the RestoreDefaultPrinter method). This way you made sure that the default printer was restored and your document is printed to novaPDF Printer.

Source code snippets

1. DECLARE INovaPdfOptions variable

```
//declare an INovaPdfOptions member variable  
PRIVATE  
    m_novaOptions : INovaPdfOptions;
```

2. Register novaPDF Printer messages

```
//register event messages  
WM_NOVAPDF2_FILESAVED := RegisterWindowMessage(MSG_NOVAPDF2_FILESAVED);  
WM_NOVAPDF2_PRINTERROR:= RegisterWindowMessage(MSG_NOVAPDF2_PRINTERROR);  
  
// handle event messages  
PUBLIC  
    PROCEDURE WndProc(var Message: TMessage); override;  
    PROCEDURE TForm1.WndProc(var Message: TMessage);  
BEGIN  
    IF Message.Msg = WM_NOVAPDF2_FILESAVED then BEGIN  
        // ...  
    END ELSE IF Message.Msg = WM_NOVAPDF2_PRINTERROR then BEGIN  
        // ...  
    END ELSE BEGIN  
        inherited WndProc(Message);  
    END;  
END;
```

3. Initialize INovaPdfOptions

```
PROCEDURE TForm1.FormCreate(Sender: TObject);  
BEGIN  
    // ...  
  
    // initialize COM libraries  
    hr := ActiveX.CoInitialize(NIL);  
    IF FAILED(hr) then BEGIN  
        MessageDlg('Failed to initialize COM' + #13+SysErrorMessage(hr) + #13+  
            SysErrorMessage(GetLastError()), mtWarning, [mbOK], 0);  
    END;  
  
    //create an instance of INovaPdfOptions  
    m_novaOptions := NIL;  
    hr := ActiveX.CoCreateInstance(  
        CLASS_NovaPdfOptions, //CLSID_CNovaPdfSource  
        NIL,  
        CLSCTX_INPROC_SERVER,  
        IID_INovaPdfOptions,  
        m_novaOptions);  
    IF (FAILED(hr)) then BEGIN  
        MessageDlg('Failed to create novaPDF COM object',  
            mtWarning, [mbOK], 0);  
    END;  
    EXIT;  
END;
```

```

//initialize NovaPdfOptions and pass printer name
//if you have an application license for novaPDF SDK,
//pass both the registration name and the license key to the Initialize2() funct
//hr := m_novaOptions.Initialize2( PRINTER_NAME, '<registration name>', '<licens
hr := m_novaOptions.Initialize2( PRINTER_NAME, '', '', '' );
IF (FAILED(hr)) then BEGIN
    MessageDlg('Failed to initialize NovaPdfOptions',
               mtWarning, [mbOK], 0);
    EXIT;
END;

// add 2 profiles in registry
CreateProfiles();

// load profiles from registry
LoadProfiles();

END;

```

4. Release INovaPDFOptions

```

PROCEDURE TForm1.FormClose(Sender: TObject; var Action: TCloseAction);
BEGIN
    //...
    //delete profiles
    hr := m_novaOptions.DeleteProfile2( SMALL_SIZE_PROFILE, PROFILE_IS_PUBLIC );
    hr := m_novaOptions.DeleteProfile2( FULL_OPT_PROFILE, PROFILE_IS_PUBLIC );

    // destroy m_novaOptions object
    // - no need for this as the Delphi takes care of it automatically

    // uninitialized COM libraries
    ActiveX.CoUninitialize();

    //...
END;

```

5. Set novaPDF Printer Options

```

PROCEDURE TForm1.CreateProfiles();
BEGIN
    // Add a profile called "Small size". if profile L"Small size" exists this will
    hr := m_novaOptions.AddProfile2(SMALL_SIZE_PROFILE, PROFILE_IS_PUBLIC);

    // Set some options to this profile

    // disable the "Save PDF file as" prompt
    hr := m_novaOptions.SetOptionLong2(NOVAPDF_SAVE_PROMPT,
                                       0,
                                       SMALL_SIZE_PROFILE,
                                       PROFILE_IS_PUBLIC);

    // set generated Pdf files destination folder to the application path
    hr := m_novaOptions.SetOptionString2(
        NOVAPDF_SAVE_FOLDER,
        ExtractFilePath(Application.ExeName),
        SMALL_SIZE_PROFILE,
        PROFILE_IS_PUBLIC);

    // set output file name
    hr := m_novaOptions.SetOptionString2(NOVAPDF_SAVE_FILE,
                                         'PDF Converter small size.pdf',

```

```

        SMALL_SIZE_PROFILE,
        PROFILE_IS_PUBLIC);

    //Set other options and profiles
    //...
END;
```

6. Start a print job

```

PROCEDURE TForm1.btnStartPrintClick(Sender: TObject);
var
    hExec : HINST;
BEGIN
    //...

    hr := S_OK;

    // set the active profile to be used for printing
    hr := m_novaOptions.SetActiveProfile2(cbProfiles.TEXT, PROFILE_IS_PUBLIC);

    // register our window to receive messages from the printer
    hr := m_novaOptions.RegisterEventWindow(SELF.Handle);

    // set novaPDF as default printer, so it will be used by ShellExecute
    hr := m_novaOptions.SetDefaultPrinter();

    //license the file to be converted with Shellexecute
    hr := m_novaOptions.LicenseShellExecuteFile(efFileToConvert.TEXT);

    // print the document
    m_bPrintJobPending := TRUE;

    hExec := ShellAPI.ShellExecute(SELF.handle,
                                   'print',
                                   PChar(efFileToConvert.TEXT),
                                   PChar(''), PChar(''), SW_HIDE);

    IF (hExec <= 32) then BEGIN // failed to execute program
        m_bPrintJobPending := FALSE;
        hr := m_novaOptions.UnRegisterEventWindow();
        hr := m_novaOptions.RestoreDefaultPrinter();
    END;

END;
```

7. Restore default printer when printing finished

```

PROCEDURE TForm1.WndProc(var Message: TMessage);
BEGIN
    IF Message.Msg = WM_NOVAPDF2_FILESAVED then BEGIN

        // restore original default printer
        hr := m_novaOptions.UnRegisterEventWindow();
        hr := m_novaOptions.RestoreDefaultPrinter();
        m_bPrintJobPending := FALSE;

    END ELSE IF Message.Msg = WM_NOVAPDF2_PRINTERROR then BEGIN

        CASE (Message.WParam) OF
            ERROR_MSG_TEMP_FILE : BEGIN
```

```

        MessageDlg('Error saving temporary file on printer server',
                  mtWarning, [mbOK], 0);
    END;
    ERROR_MSG_LIC_INFO : BEGIN
        MessageDlg('Error reading license information',
                  mtWarning, [mbOK], 0);
    END;
    ERROR_MSG_SAVE_PDF : BEGIN
        MessageDlg('Error saving PDF file', mtWarning, [mbOK], 0);
    END;
    ERROR_MSG_JOB_CANCELED : BEGIN
        MessageDlg('Print job was canceled', mtWarning, [mbOK], 0);
    END;
    END;
    // restore original default printer
    hr := m_novaOptions.UnRegisterEventWindow();
    hr := m_novaOptions.RestoreDefaultPrinter();
    m_bPrintJobPending := FALSE;

    END ELSE BEGIN

        inherited WndProc(Message);

    END;
END;
```

2.4.3.2 Hello World Delphi

Hello **World Delphi** sample is a simple Windows console application that prints one page with the "Hello World from Delphi!" text to the novaPDF Printer.

It demonstrates the basic use of the INovaPDFOptions interface. The printing job is made with calls to the global Printer object defined by Delphi. Text is printed using Canvas.TextOut method.

It generates a "Hello World.pdf" file in the working folder.

Notice

If you print an existing document using "ShellExecute()" function or you want to handle printing events, you should check the VCL Converter sample instead.

Source code

```

program HelloWorld;

{$APPTYPE CONSOLE}

uses
    ActiveX,
    Printers,
    novaOptions,
    novapiLIB_TLB;

const

    //name of novaPDF Printer
    PRINTER_NAME      = 'novaPDF Pro v5';

    //text to be written in the PDF file
    PDF_TEXT          = 'Hello world from Delphi!';
```

```
//PDF file name
PDF_FILE_NAME = 'HelloWorld_Delphi.pdf';

//Print profile name
PROFILE_NAME = 'HelloWorld Delphi Profile';
PROFILE_IS_PUBLIC = 0;

var
  hr : HRESULT;
  pNova : INovaPdfOptions;
  strDefaultProfile : WideString;
  bPublicProfile: INTEGER;
  //decomment next code if you use workaround for printer index (see below)
  //Device, Driver, Port: array[0..80] of Char;
  //DevMode: THandle;

BEGIN

  //initialize COM
  hr := ActiveX.CoInitialize(NIL);
  IF (FAILED(hr)) then BEGIN
    System.WriteLine('Failed to initialize COM');
    EXIT;
  END;

  //create one NovaPdfOptions instance
  pNova := NIL;
  hr := ActiveX.CoCreateInstance(
    CLASS_NovaPdfOptions, //CLSID_CNovaPdfSource,
    NIL,
    CLSCTX_INPROC_SERVER,
    IID_INovaPdfOptions,
    pNova);
  IF (FAILED(hr)) then BEGIN
    System.WriteLine('Failed to create novaPDF COM object');
    EXIT;
  END;

  //initialize NovaPdfOptions and pass printer name
  //if you have an application license for novaPDF SDK,
  //pass both the registration name and the license key to the Initialize2() funct
  //hr := pNova.Initialize2( PRINTER_NAME, '<registration name>', '<license key>' )
  hr := pNova.Initialize2( PRINTER_NAME, '', '', '' );

  IF (SUCCEEDED(hr)) then BEGIN

    pNova.SetDefaultPrinter();
    // now the default printer is novaPDF printer but the Printer object is not up
    // here is a workaround to update the Printer object with the default printer
    // you only need this code if you check later on the Printer.PrinterIndex to f
    //Printer.GetPrinter(Device, Driver, Port, DevMode);
    //Printer.SetPrinter(PRINTER_NAME, Driver, Port, 0);

    // set optional PDF settings
    // create a temporary profile for the current print job,
    // in order to not modify the default profile settings
```

```

pNova.AddProfile2(PROFILE_NAME, PROFILE_IS_PUBLIC);
// set PDF document Title
pNova.SetOptionString2(NOVAPDF_INFO_TITLE,
                      'Hello World Delphi Sample', PROFILE_NAME, PROFILE_IS_P

// set resulting file name
pNova.SetOptionString2(NOVAPDF_SAVE_FOLDER, '', PROFILE_NAME, PROFILE_IS_PUBLI
pNova.SetOptionString2(NOVAPDF_SAVE_FILE,
                      PDF_FILE_NAME, PROFILE_NAME, PROFILE_IS_PUBLIC);

//do not show prompt dialog
pNova.SetOptionLong2(NOVAPDF_SAVE_PROMPT, 0, PROFILE_NAME, PROFILE_IS_PUBLIC);
//if file exists, override
pNova.SetOptionLong2(NOVAPDF_SAVE_CONFLICT_STRATEGY,
                    FILE_CONFLICT_STRATEGY_OVERWRITE,
                    PROFILE_NAME, PROFILE_IS_PUBLIC);

//open document in PDF viewer
pNova.SetOptionLong2(NOVAPDF_ACTION_OPEN_DOCUMENT, 1, PROFILE_NAME, PROFILE_IS
// set active profile
strDefaultProfile := '';
pNova.GetActiveProfile2(strDefaultProfile, bPublicProfile);
pNova.SetActiveProfile2(PROFILE_NAME, PROFILE_IS_PUBLIC);

//start print job
Printer.BeginDoc();
Printer.Canvas.Font.Size := 24;
Printer.Canvas.TextOut( 100,
                      80,
                      PDF_TEXT);

Printer.endDoc();
System.WriteLine('Print job finished');

//restore default profile
pNova.SetActiveProfile2(strDefaultProfile, bPublicProfile);
pNova.DeleteProfile2(PROFILE_NAME, PROFILE_IS_PUBLIC);
//restore default printer
pNova.RestoreDefaultPrinter();
END ELSE BEGIN
  System.WriteLine('Failed to initialize novaPDF Printer');
END;

ActiveX.CoUninitialize();

END.

```

2.4.3.3 Word OLE Delphi

The **Word OLE Delphi** sample is a simple Windows console application that converts a MS Word document (C:\Test.doc) to PDF using Word OLE automation.

Source code

```

program WordOLEDelphi;

{$APPTYPE CONSOLE}

uses
  ActiveX,
  Printers,
  ComObj,
  SysUtils,

```

```
Dialogs,
novaOptions,
novapiLIB_TLB;

Const

    //name of novaPDF Printer
    PRINTER_NAME      = 'novaPDF Pro v5';

    //Print profile name
    PROFILE_NAME      = 'Test OLE Delphi Profile';
    PROFILE_IS_Public = 0;

var
    hr : HRESULT;
    pNova : INovaPdfOptions;
    strDefaultProfile : WideString;
    WORD : VARIANT;
    NewDoc : VARIANT;
    bPublicProfile: INTEGER;

BEGIN
    //initialize COM
    hr := ActiveX.CoInitialize(NIL);
    IF (FAILED (hr)) then BEGIN
        System.WriteLine('Failed to initialize COM');
        EXIT;
    END;

    //create one NovaPdfOptions instance
    pNova := NIL;
    hr := ActiveX.CoCreateInstance(
        CLASS_NovaPdfOptions, //CLSID_CNovaPdfSource,
        NIL,
        CLSCTX_INPROC_SERVER,
        IID_INovaPdfOptions,
        pNova);
    IF (FAILED(hr)) then BEGIN
        System.WriteLine('Failed to create novaPDF COM object');
        EXIT;
    END;

    //initialize NovaPdfOptions and pass printer name
    //if you have an application license for novaPDF SDK,
    //pass both the registration name and the license key to the Initialize2() funct
    //hr := pNova.Initialize2( PRINTER_NAME, '<registration name>', '<license key>' )
    hr := pNova.Initialize2( PRINTER_NAME, '', '', '' );

    IF (SUCCEEDED(hr)) then BEGIN

        pNova.SetDefaultPrinter();
        // now the default printer is novaPDF printer but the Printer object is not up
        // here is a workaround to update the Printer object with the default printer
        // you only need this code if you check later on the Printer.PrinterIndex to f
        //Printer.GetPrinter(Device, Driver, Port, DevMode);
        //Printer.SetPrinter(PRINTER_NAME, Driver, Port, 0);

        // set optional PDF settings
```

```

// create a temporary profile for the current print job,
// in order to not modify the default profile settings
pNova.AddProfile2(PROFILE_NAME, PROFILE_IS_PUBLIC);
// set PDF document Title
pNova.SetOptionString2(NOVAPDF_INFO_TITLE,
                       'Hello World Delphi Sample', PROFILE_NAME, PROFILE_IS_P
// set resulting file name
pNova.SetOptionString2(NOVAPDF_SAVE_FOLDER, 'C:\', PROFILE_NAME, PROFILE_IS_PU
//do not show prompt dialog
pNova.SetOptionLong2(NOVAPDF_SAVE_PROMPT, 0, PROFILE_NAME, PROFILE_IS_PUBLIC);
//if file exists, override
pNova.SetOptionLong2(NOVAPDF_SAVE_CONFLICT_STRATEGY,
                     FILE_CONFLICT_STRATEGY_OVERWRITE,
                     PROFILE_NAME, PROFILE_IS_PUBLIC);
//open document in PDF viewer
pNova.SetOptionLong2(NOVAPDF_ACTION_OPEN_DOCUMENT, 1, PROFILE_NAME, PROFILE_IS
// set active profile
strDefaultProfile := '';
pNova.GetActiveProfile2(strDefaultProfile, bPublicProfile);
pNova.SetActiveProfile2(PROFILE_NAME, PROFILE_IS_PUBLIC);

//Print Word Document
try
  pNova.InitializeOLEUsage('Word.Application');
  WORD := CreateOleObject('Word.Application');
  WORD.DisplayAlerts := 0;
  pNova.LicenseOLEServer();
  NewDoc:= WORD.Documents.Open('C:\Test.doc', FALSE, TRUE);
  NewDoc.PrintOut(FALSE);
  NewDoc.Close(FALSE);
  WORD.Quit(FALSE);
except
  on E: Exception DO
    ShowMessage(E.Message);
END;

//restore default profile
pNova.SetActiveProfile2(strDefaultProfile, bPublicProfile);
pNova.DeleteProfile2(PROFILE_NAME, PROFILE_IS_PUBLIC);
//restore default printer
pNova.RestoreDefaultPrinter();
END ELSE BEGIN
  System.WriteLine('Failed to initialize novaPDF Printer');
END;

ActiveX.CoUninitialize();

END.

```

2.4.4 C#

2.4.4.1 Hello World CSharp

Hello World CSharp sample is a simple Windows console application that prints one page with the "novaPDF says Hello World from C#" text to the novaPDF Printer.

It demonstrates the basic use of the `INovaPDFOptions` interface. The printing job is made using the package "System.Drawing.Printing"

Basically the sample determines the active profile, makes a copy of it into a profile called "Test C#", sets the new profile as active, sets the subject of the generated PDF document, prints a page, and restores original printer settings. The location of the generated document depends on whatever the settings are for the current active profile.

Notice

Because of the specific exception based error handling in .NET, all calls to methods in the INovaPDFOptions interface must be nested within a try-catch block. Consider for example that we want to add a profile called "test", but the profile "test" already exists. Then the call pNova.AddProfile("test") will throw an "System.Runtime.InteropServices.COMException". with the ErrorCode property set to NV_PROFILE_EXISTS (0xD5DA0006).

Source code

```
USING System;
USING System.Drawing;
USING System.Drawing.Printing;
USING System.Windows.Forms;
// the novapiLib package must be added as a COM reference
USING novapiLib;

namespace Hello_World_CSharp
{
    /// <summary>
    /// Summary description for Class1.
    /// </summary>
    CLASS Class1
    {
        /// <summary>
        /// The main entry point for the application.
        /// </summary>
        PUBLIC STATIC STRING PRINTER_NAME = "novaPDF Pro v5";
        PUBLIC STATIC STRING NOVAPDF_INFO_SUBJECT = "Document Subject";
        PUBLIC STATIC uint NV_PROFILE_EXISTS = 0xD5DA0006;
        PUBLIC STATIC STRING PROFILE_NAME = "Test C#";
        PUBLIC STATIC INT PROFILE_IS_PUBLIC = 0;

        [STAThread]
        STATIC VOID Main(STRING[] args)
        {
            try
            {
                // create the NovaPdfOptions object
                NovaPdfOptions pNova = new NovaPdfOptions();
                // initialize the NovaPdfOptions object
                // if you have an application license for novaPDF SDK,
                // pass both the registration name and the license key to the Initialize()
                // pNova.Initialize(PRINTER_NAME, "<registration name>", "<license key>",
                pNova.Initialize(PRINTER_NAME, "", "", "");
                // get the active profile ...
                STRING activeProfile;
                INT nActivePublic;
                pNova.GetActiveProfile(out activeProfile, out nActivePublic);
                try
                {
                    // and make a copy of it
                    pNova.CopyProfile(activeProfile, PROFILE_NAME, PROFILE_IS_PUBLIC);
                }
            }
        }
    }
}
```

```

    }
    catch (System.Runtime.InteropServices.COMException e)
    {
        // ignore profile exists error
        IF (NV_PROFILE_EXISTS == e.ErrorCode)
        {
            System.Console.WriteLine("Profile Test C# already exists");
        }
        ELSE
        {
            // more serious error, propagate it
            throw e;
        }
    }

    // set the copy profile as active profile ...
    pNova.SetActiveProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);
    // and set some options
    pNova.SetOptionString(NOVAPDF_INFO_SUBJECT, "C# Hello document", PROFILE_N

    // print a test page, using the previously set active profile settin
    USING (PrintDocument pd = new PrintDocument())
    {
        pd.PrinterSettings.PrinterName = PRINTER_NAME;
        pd.PrintPage += new PrintPageEventHandler(PrintPageFunction);
        pd.Print();
    }

    pNova.SetActiveProfile(activeProfile, nActivePublic);
    pNova.DeleteProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);
}
catch (System.Runtime.InteropServices.COMException e)
{
    MessageBox.Show(e.Message);
}
catch (Exception e)
{
    MessageBox.Show(e.Message);
}
}
// and finally the function that actually prints the page
PRIVATE STATIC VOID PrintPageFunction(OBJECT sender, PrintPageEventArgs ev)
{
    STRING STR = "novaPDF says Hello World from C#";
    Font font = new Font("Arial", 16);
    Brush brush = new SolidBrush(Color.Black);
    ev.Graphics.DrawString(STR, font, brush, 20.0f, 20.0f);
    ev.HasMorePages = FALSE;
}
}
}
}

```

2.4.4.2 CSharp Converter

The **CSharp Converter** sample demonstrates how to convert an existing file by printing it to novaPDF Printer using the ShellExecute function. It also demonstrates how to set different options and manage profiles.

The same approach should be taken if you print using a "Print()" method from another object (like

an internet browser or a report control). Just replace the ShellExecute call with the call of your Print method.

When the application starts, it creates a few profiles and makes different settings in the profiles. Then it shows a dialog from where the user can select the active profile and change its settings using the controls from the dialog.

After that a document can be selected from the harddisk and printed to novaPDF Printer using the ShellExecute function call.

When using this technique to convert a file to PDF, you have to take care of the fact that ShellExecute prints to the default printer. This function returns immediately and does not wait until the print is finished (it may return before the printing is actually started). Therefore you have to set the default printer to novaPDF Printer before calling ShellExecute (using the SetDefaultPrinter method), wait the process to be started (using WaitForExit()), restore the default printer (with the RestoreDefaultPrinter method). This way you made sure that the default printer was restored and your document is printed to novaPDF Printer.

Source code snippets

1. DECLARE INovaPdfOptions variable

```
PRIVATE NovaPdfOptionsClass mobjNovaOptios;
```

2. Initialize INovaPdfOptions

```
mobjNovaOptios = new NovaPdfOptionsClass();

// initialize the NovaPdfOptions object
// if you have an application license for novaPDF SDK,
// pass both the registration name and the license key to the Initialize() functi
// mobjNovaOptios.Initialize(PRINTER_NAME, "<registration name>", "<license key>");
mobjNovaOptios.Initialize(PRINTER_NAME, "", "", "");

AddSmallProfile();
AddFullProfile();
```

3. Set novaPDF Printer Options

```
try
{
    mobjNovaOptios.AddProfile2(SMALL_SIZE_PROFILE);
    // Set some options to this profile
    // disable the "Save PDF file as" prompt
    mobjNovaOptios.SetOptionLong2(NovaOptions.NOVPDF_SAVE_PROMPT, 0, SMALL_SIZE_P
    // set generated Pdf files destination folder "c:\"
    mobjNovaOptios.SetOptionString2(NovaOptions.NOVPDF_SAVE_FOLDER, "c:\\", SMALL

    // .....
}
catch(System.Runtime.InteropServices.COMException ComException)
{
    IF (((~ComException.ErrorCode ^ NovaErrors.NV_PROFILE_EXISTS) ^ 0xFFFFFFFF)==0)
    {
        System.Diagnostics.Debug.WriteLine("Profile \"Small Size Profile\" exists");
    }
    ELSE
```

```

    {
        MessageBox.Show("Error creating Small Size Profile:\r\n" + ComException.Message);
        System.Diagnostics.Debug.WriteLine(ComException.Message);
    }
}

```

4. Start a print job

```

PRIVATE VOID btnStartPrinting_Click(OBJECT sender, System.EventArgs e)
{
    UpdateProfileFromDialog();
    mobjNovaOptios.SetActiveProfile2((STRING)(cmbProfiles.SelectedItem));
    mobjNovaOptios.SetDefaultPrinter();

    mobjNovaOptios.LicenseShellExecuteFile(txtFileToConvert.TEXT);

    Process myProcess = new Process();
    try
    {
        myProcess.StartInfo.FileName = txtFileToConvert.TEXT;
        myProcess.StartInfo.Verb = "Print";
        myProcess.StartInfo.CreateNoWindow = TRUE;
        myProcess.Start();
    }
    catch (Win32Exception ex)
    {
        IF(ex.NativeErrorCode == ERROR_FILE_NOT_FOUND)
        {
            Console.WriteLine(ex.Message + ". Check the path and filename");
        }
        ELSE IF (ex.NativeErrorCode == ERROR_ACCESS_DENIED)
        {
            // Note that if your word processor might generate exceptions
            // such as this, which are handled first.
            Console.WriteLine(ex.Message + ". You do not have permission to print this f
        }
    }
    myProcess.WaitForExit(10000);
    myProcess.Close();
    mobjNovaOptios.RestoreDefaultPrinter();
}

```

2.4.4.3 Word OLE CSharp

The **Word OLE CSharp** sample is a simple Windows console application that converts a MS Word document (C:\Test.doc) to PDF using Word OLE automation.

Source code

```

USING System;
USING System.Drawing;
USING System.Drawing.Printing;
USING System.Windows.Forms;
// the novapiLib package must be added as a COM reference
USING novapiLib;

namespace Hello_World_CSharp
{
    /// <summary>

```

```
/// Summary description for Class1.
/// </summary>
CLASS Class1
{
    /// <summary>
    /// The main entry point for the application.
    /// </summary>
    PUBLIC STATIC STRING PRINTER_NAME = "novaPDF Pro v5";
    PUBLIC STATIC STRING NOVAPDF_INFO_SUBJECT = "Document Subject";
    PUBLIC STATIC STRING PROFILE_NAME = "Test C# OLE";
    PUBLIC STATIC INT PROFILE_IS_PUBLIC = 0;
    PUBLIC STATIC uint NV_PROFILE_EXISTS = 0xD5DA0006;

    [STAThread]
    STATIC VOID Main(STRING[] args)
    {
        try
        {
            // create the NovaPdfOptions object
            NovaPdfOptions pNova = new NovaPdfOptions();
            // initialize the NovaPdfOptions object
            // if you have an application license for novaPDF SDK,
            // pass both the registration name and the license key to the Initialize()
            // pNova.Initialize(PRINTER_NAME, "<registration name>", "<license key>",
            pNova.Initialize(PRINTER_NAME, "", "", "");
            // get the active profile ...
            STRING activeProfile;
            INT nActivePublic;
            pNova.GetActiveProfile(out activeProfile, out nActivePublic);
            try
            {
                // and make a copy of it
                pNova.CopyProfile(activeProfile, PROFILE_NAME, PROFILE_IS_PUBLIC);
            }
            catch (System.Runtime.InteropServices.COMException e)
            {
                // ignore profile exists error
                IF (NV_PROFILE_EXISTS == e.ErrorCode)
                {
                    System.Console.WriteLine("Profile Test C# OLE already exists");
                }
                ELSE
                {
                    // more serious error, propagate it
                    throw e;
                }
            }
            // set the copy profile as active profile ...
            pNova.SetActiveProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);
            // and set some options
            pNova.SetOptionString(NOVAPDF_INFO_SUBJECT, "C# Hello document", PROFILE_N
            // set nova default printer
            pNova.SetDefaultPrinter();
            // initialize OLE usage in novaPDF
            pNova.InitializeOLEUsage("Word.Application");
            // create Word application object
            WORD._Application WordApp = new WORD.Application();
        }
    }
}
```



```
//Include novaPDF headers
#include "..\..\include\novaOptions.h"
#include "..\..\include\novapi.h"

//name of novaPDF Printer
#define PRINTER_NAME L"novaPDF Pro v5"

//text to be written in the PDF file
#define PDF_TEXT L"Hello world!"

//PDF file name
#define PDF_FILE_NAME L"HelloWorld.pdf"

//Print profile name
#define PROFILE_NAME L"HelloWorld Profile"
#define PROFILE_IS_PUBLIC 0

//entry point for the console application
int _tmain(int argc, _TCHAR* argv[])
{
    HRESULT hr = S_OK;

    //initialize COM
    hr = CoInitialize(NULL);
    if (FAILED (hr))
    {
        MessageBox(NULL, L"Failed to initialize COM", L"novaPDF", MB_OK);
        return hr;
    }

    //create one NovaPdfOptions instance
    INovaPdfOptions *pNova = 0;
    hr = CoCreateInstance(__uuidof(NovaPdfOptions), NULL, CLSCTX_INPROC_SERVER, __uuidof(INovaPdfOptions), &pNova);
    if (FAILED(hr))
    {
        MessageBox(NULL, L"Failed to create novaPDF COM object", L"novaPDF", MB_OK);
        return hr;
    }

    //initialize NovaPdfOptions and pass printer name
    //if you have an application license for novaPDF SDK,
    //pass both the registration name and the license key to the Initialize() function
    //hr = pNova->Initialize(PRINTER_NAME, L"<registration name>", L"<license key>");
    hr = pNova->Initialize(PRINTER_NAME, L"", L""), L"";

    if (SUCCEEDED(hr)) {

        pNova->SetDefaultPrinter();
        // set optional PDF settings
        // create a temporary profile for the current print job,
        // in order to not modify the default profile settings
        pNova->AddProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);
        // set PDF document Title
        pNova->SetOptionString(NOVAPDF_INFO_TITLE, L"Hello World Sample",
            PROFILE_NAME, PROFILE_IS_PUBLIC);
        // set resulting file name
        pNova->SetOptionString(NOVAPDF_SAVE_FOLDER, L"",
```

```

        PROFILE_NAME, PROFILE_IS_PUBLIC);
pNova->SetOptionString(NOVAPDF_SAVE_FILE, PDF_FILE_NAME,
        PROFILE_NAME, PROFILE_IS_PUBLIC);
//do not show prompt dialog
pNova->SetOptionLong(NOVAPDF_SAVE_PROMPT, 0,
        PROFILE_NAME, PROFILE_IS_PUBLIC);
//if file exists, override
pNova->SetOptionLong(NOVAPDF_SAVE_CONFLICT_STRATEGY,
        FILE_CONFLICT_STRATEGY_OVERWRITE,
        PROFILE_NAME, PROFILE_IS_PUBLIC);
// set active profile
LPWSTR wsDefaultProfile = NULL;
int nDefProfilePublic = 0;
pNova->GetActiveProfile(&wsDefaultProfile, &nDefProfilePublic);
pNova->SetActiveProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);

HANDLE hPrinter;
PDEVMODEW pDevmode = NULL;
PRINTER_DEFAULTS pd = { NULL, NULL, PRINTER_ACCESS_USE };

//start print job
if (OpenPrinter(PRINTER_NAME, &hPrinter, &pd))
{
    //get default printer DEVMODE
    int nSize = DocumentProperties(NULL, hPrinter, PRINTER_NAME, NULL, NULL, 0);
    pDevmode = (PDEVMODEW)LocalAlloc(LPTR, nSize);
    DocumentProperties(NULL, hPrinter, PRINTER_NAME, pDevmode, NULL, DM_OUT_DEFA

    //Print a page
    HDC hDC = CreateDC(L"", PRINTER_NAME, NULL, pDevmode);
    DOCINFO docInfo = {sizeof(DOCINFO)};
    // PDF document name and path
    docInfo.lpszDocName = PDF_FILE_NAME;
    StartDoc(hDC, &docInfo);
    StartPage(hDC);
    // Draw text on page
    TextOut(hDC, 100, 80, PDF_TEXT, (int) wcslen(PDF_TEXT));
    EndPage(hDC);
    EndDoc(hDC);
    DeleteDC(hDC);

    //print job sent to printer
    MessageBox(NULL, L"Print job finished", L"novaPDF", MB_OK);

    LocalFree(pDevmode);
    ClosePrinter(hPrinter);
}
else
{
    WCHAR wsMessage[255];
    wsprintf(wsMessage, L"OpenPrinter failed, error = %d", GetLastError());
    MessageBox(NULL, wsMessage, L"novaPDF", MB_OK);
}
//restore default profile
pNova->SetActiveProfile(wsDefaultProfile, nDefProfilePublic);
pNova->DeleteProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);
CoTaskMemFree(wsDefaultProfile);
//restore default printer

```



```

        pNova->RestoreDefaultPrinter();
    }
    else{
        MessageBox(NULL, L"Failed to initialize novaPDF Printer", L"novaPDF", MB_OK);
    }

    //release NovaPdfOptions
    pNova->Release();
    CoUninitialize();
    return 0;
}

```

2.4.5.2 Hello World (network)

Hello World (network) sample is similar with Hello World sample but it adds network functionality:

- it requests the shared printer name in a dialog as "\\computer name\printer name" (for example if novaPDF Pro is installed on WS1, then you should enter "\\WS1\novaPDF Pro v4")
- it automatically registers novapi4.dll if not registered. novapi4.dll must be in the same folder with the HelloWorld (network).exe file.

You can share the folder containing HelloWorld (network).exe and novapi4.dll on your network and run the executable from any other computer in the network, with no need to install anything else. It will generate a "HelloWorldNet.pdf" file in the same folder.

Source Code snippets (in addition to Hello World source code)

```

{
    //...
    //initialize COM
    hr = CoInitialize(NULL);
    if (FAILED (hr))
    {
        MessageBoxW(NULL, L"Failed to initialize COM", L"novaPDF", MB_OK);
        return hr;
    }

    // register the novapi2.dll COM module found in this executable's directory
    hr = RegisterNovaCOM(TRUE);

    //create one NovaPdfOptions instance
    INovaPdfOptions *pNova = 0;
    hr = CoCreateInstance(__uuidof(NovaPdfOptions), NULL, CLSCTX_INPROC_SERVER, __u
    if (FAILED(hr))
    {
        MessageBoxW(NULL, L"Failed to create novaPDF COM object", L"novaPDF", MB_OK);
        return hr;
    }
    DWORD dwSize = 256;
    WCHAR strWorkStation[256];

    //find out computer name
    GetComputerNameW(strWorkStation, &dwSize);

    PrinterNameDlg dlg;
    //construct printer name as "\\computer name\printer name"
    dlg.m_strPrinterName.Format(L"\\\\%s\\%s", strWorkStation, PRINTER_NAME);
}

```

```

    //get printer name from user
    if (IDCANCEL == dlg.DoModal())
    {
        pNova->Release();
        CoUninitialize();
        return hr;
    }
    CString strPrinterName = dlg.m_strPrinterName;

    //initialize NovaPdfOptions and pass printer name
    // if you have an application license for novaPDF SDK,
    // pass both the registration name and the license key to the Initialize() funct
    // hr = pNova->Initialize((LPCWSTR)strPrinterName, L"<registration name>", L"<li
    hr = pNova->Initialize((LPCWSTR)strPrinterName, L"", L"", L "");
    //...
}

//Register novaPDF COM from novapi2.dll
//novapi2.dll should be in the same folder with the application
HRESULT RegisterNovaCOM(BOOL bRegister = TRUE)
{
    HRESULT hr = E_FAIL;
    WCHAR szFileName[_MAX_PATH] = L"";

    //find out application path and name
    DWORD dwRes = GetModuleFileNameW(NULL, szFileName, _MAX_PATH);

    if (dwRes > 0 && dwRes < _MAX_PATH)
    {
        WCHAR szDir[_MAX_PATH], szDrive[_MAX_DRIVE];

        //get application path
        _wsplitpath(szFileName, szDrive, szDir, NULL, NULL);
        wcscpy(szFileName, szDrive);
        wcscat(szFileName, szDir);
    }

    //add COM dll name
    wcscat(szFileName, L"novapi5.dll");

    //load COM dll
    HMODULE hNova = LoadLibraryW(szFileName);

    typedef HRESULT (STDAPICALLTYPE *DllRegisterServerFunction)(void);
    DllRegisterServerFunction fun = NULL;

    if (hNova)
    {
        if (bRegister)
        {
            //get the address of DllRegisterServer function
            fun = (DllRegisterServerFunction) GetProcAddress(hNova, "DllRegisterServer")
        }
        else
        {
            //get the address of DllUnregisterServer function
            fun = (DllRegisterServerFunction) GetProcAddress(hNova, "DllUnregisterServer")
        }
    }
}

```

```
    }  
    if (fun)  
    {  
        // call DllRegisterServer (or DllUnregisterServer)  
        hr = fun();  
    }  
    return hr;  
}
```

2.4.5.3 MFC Converter

The **MFC Converter** sample demonstrates how to convert an existing file by printing it to novaPDF Printer using the ShellExecute function. It also demonstrates how to set different options and manage profiles.

The same approach should be taken if you print using a "Print()" method from another object (like an internet browser or a report control). Just replace the ShellExecute call with the call of your Print method.

When the application starts, it creates a few profiles and makes different settings in the profiles. Then it shows a dialog from where the user can select the active profile and change its settings using the controls from the dialog.

After that a document can be selected from the harddisk and printed to novaPDF Printer using the ShellExecute function call.

When using this technique to convert a file to PDF, you have to take care of the fact that ShellExecute prints to the default printer. This function returns immediately and does not wait until the print is finished (it may return before the printing is actually started). Therefore you have to set the default printer to novaPDF Printer before calling ShellExecute (using the SetDefaultPrinter method), register FileSaved message (or any other novaPDF Printer message) to be sure that the print job was started. In this message handler restore the default printer (with the RestoreDefaultPrinter method). This way you made sure that the default printer was restored and your document is printed to novaPDF Printer.

Source code snippets

1. Declare INovaPdfOptions variable

```
//declare an INovaPdfOptions member variable  
private :  
    INovaPdfOptions *m_novaOptions;
```

2. Register novaPDF Printer messages

```
const UINT  wm_Nova_FileSaved = RegisterWindowMessageW( MSG_NOVAPDF2_FILESAVED );  
const UINT  wm_Nova_PrintError = RegisterWindowMessageW( MSG_NOVAPDF2_PRINTERROR );  
  
BEGIN_MESSAGE_MAP(CnovaPrintDlg, CDialog)  
  
    //...  
  
    ON_REGISTERED_MESSAGE(wm_Nova_FileSaved, OnNovaPDFFileSaved)  
    ON_REGISTERED_MESSAGE(wm_Nova_PrintError, OnNovaPDFPrintError)  
  
    //...  
  
END_MESSAGE_MAP( )
```

3. Initialize INovaPdfOptions

```

BOOL CnovaPrintDlg::OnInitDialog()
{
    //...

    HRESULT hr = S_OK;
    m_novaOptions = 0;

    //create an instance of INovaPdfOptions
    hr = CoCreateInstance(__uuidof(NovaPdfOptions), NULL, CLSCTX_INPROC_SERVER, __
    if (SUCCEEDED(hr)) {
        //initialize NovaPdfOptions and pass printer name
        // if you have an application license for novaPDF SDK,
        // pass both the registration name and the license key to the Initialize()
        // hr = m_novaOptions->Initialize(PRINTER_NAME, L"<registration name>", L"
        hr = m_novaOptions->Initialize(PRINTER_NAME, L"", L"", L"");
    }
    else {
        ::MessageBoxW(NULL, L"Failed to create novaPDF COM object", L"novaPDF", MB
    }
    //...
}

```

4. Release INovaPDFOptions

```

CnovaPrintDlg::~CnovaPrintDlg()
{
    //...

    //delete profiles
    m_novaOptions->DeleteProfile(SMALL_SIZE_PROFILE, PROFILE_IS_PUBLIC);

    // destroy our nova options object
    if (m_novaOptions) {
        m_novaOptions->Release();
    }
    // uninitialized COM libraries
    CoUninitialize();

    //...
}

```

5. Set novaPDF Printer Options

```

BOOL CnovaPrintDlg::OnInitDialog()
{
    //...
    //initialize m_novaOptions (see above)
    //...

    // Add a profile called "Small size". If profile L"Small size" exists this will
    hr = m_novaOptions->AddProfile(SMALL_SIZE_PROFILE, PROFILE_IS_PUBLIC);

    // Set some options to this profile

    // disable the "Save PDF file as" prompt

```

```

hr = m_novaOptions->SetOptionLong(NOVAPDF_SAVE_PROMPT, FALSE, SMALL_SIZE_PROFILE);
// set generated Pdf files destination folder ("c:\")
hr = m_novaOptions->SetOptionString(NOVAPDF_SAVE_FOLDER, L"", SMALL_SIZE_PROFILE);
// set output file name
hr = m_novaOptions->SetOptionString(NOVAPDF_SAVE_FILE, L"PDF Converter small s

//Set other options
//...
}

```

6. Start a print job

```

void CnovaPrintDlg::OnBnClickedOk()
{
    //...

    HRESULT hr = S_OK;

    // set the active profile to be used for printing
    hr = m_novaOptions->SetActiveProfile(m_strProfile, PROFILE_IS_PUBLIC);

    // register our window to receive messages from the printer
    hr = m_novaOptions->RegisterEventWindow((LONG) GetSafeHwnd());

    // set novaPDF as default printer, so it will be used by ShellExecute
    hr = m_novaOptions->SetDefaultPrinter();

    // license file for ShellExecute
    hr = m_novaOptions->LicenseShellExecuteFile(m_strFileToConvert.AllocSysString());

    // print the document
    m_bPrintJobPending = TRUE;
    HINSTANCE hExec = ShellExecute(GetSafeHwnd(), L"print", m_strFileToConvert, NU

    //...
}

```

7. Restore default printer when printing finished

```

LRESULT CnovaPrintDlg::OnNovaPDFFileSaved(WPARAM wParam, LPARAM lParam)
{
    // restore original default printer
    m_novaOptions->UnRegisterEventWindow();
    m_novaOptions->RestoreDefaultPrinter();
    m_bPrintJobPending = FALSE;
    return 0;
}

LRESULT CnovaPrintDlg::OnNovaPDFPrintError(WPARAM wParam, LPARAM lParam)
{
    switch(wParam){
        case ERROR_MSG_TEMP_FILE:
            MessageBox(L"Error saving temporary file on printer server", L"novaPDF", MB_OK);
            break;
        case ERROR_MSG_LIC_INFO:
            MessageBox(L"Error reading license information", L"novaPDF", MB_OK);
            break;
        case ERROR_MSG_SAVE_PDF:

```

```

        MessageBox(L"Error saving PDF file", L"novaPDF", MB_OK);
        break;
    case ERROR_MSG_JOB_CANCELED:
        MessageBox(L"Print job was canceled", L"novaPDF", MB_OK);
        break;
    }
    // restore original default printer
    m_novaOptions->UnRegisterEventWindow();
    m_novaOptions->RestoreDefaultPrinter();
    m_bPrintJobPending = FALSE;
    return 0;
}

```

2.4.5.4 MFC Scribble

The **MFC Scribble** sample extends the standard MFC Scribble sample with the generation of PDF files using novaPDF Printer. It demonstrates how to integrate novaPDF SDK in a document/view MFC architecture:

Source code snippets

1. Register novaPDF Printer event

```

#define PROFILE_NAME        L"MFCs Scribble Profile"
#define PDF_FILE_NAME      L"MFCs Scribble.pdf"
#define PROFILE_IS_PUBLIC  0

// This message is sent when the PDF file is finished and saved on the harddisk
const UINT  wm_Nova_FileSaved = RegisterWindowMessageW( MSG_NOVAPDF2_FILESAVED );
BEGIN_MESSAGE_MAP(CScribbleView, CScrollView)
   //{{AFX_MSG_MAP(CScribbleView)
    //...
    //}}AFX_MSG_MAP
    //...
    ON_REGISTERED_MESSAGE(wm_Nova_FileSaved, OnNovaPDFFileSaved)
END_MESSAGE_MAP()

```

2. Initialize INovaPDFOptions

```

CScribbleView::CScribbleView()
{
    //...
    HRESULT hr = CoInitialize(NULL);
    //...
    //create novaPDFOptions object
    hr = CoCreateInstance(__uuidof(NovaPdfOptions), NULL, CLSCTX_INPROC_SERVER, __uuidof(INovaPDFOptions));
    //...
    //initialize novaPDFOptions object with desired printer name
    // if you have an application license for novaPDF SDK,
    // pass both the registration name and the license key to the Initialize() function
    // m_pNova->Initialize(L"novaPDF Pro v5", L"<registration name>", L"<license key>");
    m_pNova->Initialize(L"novaPDF Pro v5", L"", L"", L"");
}

```

3. Release INovaPDFOptions

```

CScribbleView::~CScribbleView()
{
    //release novaPDFOptions object
    if (m_pNova){

```

```

        m_pNova->Release();
    }
    CoUninitialize();
}

```

4. Set novaPDF Printer Options

```

BOOL CScribbleView::OnPreparePrinting(CPrintInfo* pInfo)
{
    //set novaPDF default printer
    if (m_pNova) {
        m_pNova->SetDefaultPrinter();

        // create a temporary profile for the current print job,
        // in order to not modify the default profile settings
        m_pNova->AddProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);
        // set PDF document Title
        m_pNova->SetOptionString(NOVAPDF_INFO_TITLE, L"MFC Scribble Sample", PROFILE_NAME);
        // set resulting file name
        m_pNova->SetOptionString(NOVAPDF_SAVE_FOLDER, L"", PROFILE_NAME, PROFILE_IS_PUBLIC);
        m_pNova->SetOptionString(NOVAPDF_SAVE_FILE, PDF_FILE_NAME, PROFILE_NAME, PROFILE_IS_PUBLIC);
        //do not show prompt dialog
        m_pNova->SetOptionLong(NOVAPDF_SAVE_PROMPT, 0, PROFILE_NAME, PROFILE_IS_PUBLIC);
        //if file exists, override
        m_pNova->SetOptionLong(NOVAPDF_SAVE_CONFLICT_STRATEGY, FILE_CONFLICT_STRATEGY_REPLACE);

        // set active profile
        m_pNova->GetActiveProfile(&m_wsDefaultProfile, &m_nActiveProfilePublic);
        m_pNova->SetActiveProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);

        //register window to receive messages from novaPDF printer
        m_pNova->RegisterEventWindow((LONG)m_hWnd);
    }
    //...
}

```

5. Restore options when printing finished

```

void CScribbleView::OnEndPrinting(CDC* /*pDC*/, CPrintInfo* /*pInfo*/)
{
    if (m_pNova) {
        //unregister events
        m_pNova->UnRegisterEventWindow();
        //restore default profile
        m_pNova->SetActiveProfile(m_wsDefaultProfile, &m_nActiveProfilePublic);
        m_pNova->DeleteProfile(PROFILE_NAME, PROFILE_IS_PUBLIC);
        CoTaskMemFree(m_wsDefaultProfile);
        //restore default printer
        m_pNova->RestoreDefaultPrinter();
    }
}

```

6. novaPDF Printer message handler

```

LRESULT CScribbleView::OnNovaPDFFileSaved(WPARAM, LPARAM)
{
    //PDF is saved, so just show a message that the conversion to PDF was successful
    MessageBox(L"PDF file was saved successfully", L"novaPrint");
    return 0;
}

```

2.4.6 VB

2.4.6.1 Hello World VB

Hello World VB sample is a simple Windows console application that prints one page with the "novaPDF says Hello World from VB" text to the novaPDF Printer. It demonstrates the basic use of the INovaPDFOptions interface. The printing job is made with calls to the global Printer object defined by VB. It generates a "HelloWorld.pdf" file and opens it in the default PDF viewer.

Notice

If you print an existing document using "ShellExecute()" function or you want to handle printing events, you should check the VB Converter sample instead.

Source code

```
' the novapiLib package must be added as a COM reference
Const PRINTER_NAME As String = "novaPDF Pro v5"
Const PROFILE_IS_Public As Long = 0

' The main entry point for the application.
Public Sub Main()
    On Error GoTo ErrorHandler:

    ' create the NovaPdfOptions object
    Dim pNova As New NovaPdfOptions

    ' initialize the NovaPdfOptions object
    ' if you have an application license for novaPDF SDK,
    ' pass both the registration name and the license key to the Initialize() function
    ' pNova.Initialize2 PRINTER_NAME, '<registration name>', '<license key>'
    pNova.Initialize2 PRINTER_NAME, "", "", ""
    ' get the active profile ...
    Dim activeProfile As String
    Dim bPublicProfile As Long

    pNova.GetActiveProfile2 activeProfile, bPublicProfile
    ' and make a copy of it
    On Error Resume Next
    pNova.CopyProfile2 activeProfile, "Test VB", PROFILE_IS_Public
    If Err.Number <> 0 Then
        ' ignore profile exists error
        If NV_PROFILE_EXISTS = Err.Number Then
            Debug.Print "Profile Test VB already exists"
        Else
            Return
        End If
    End If
    On Error GoTo ErrorHandler:
    ' set the copy profile as active profile ...
    pNova.SetActiveProfile2 "Test VB", PROFILE_IS_Public
    ' and set some options
    pNova.SetOptionString2 NOVAPDF_INFO_SUBJECT, "VB Hello document", "", PROFILE_

    ' Print a test page
    Dim myPrinter As Printer

    For Each myPrinter In Printers
```



```
        If myPrinter.DeviceName = PRINTER_NAME Then
            Set Printer = myPrinter
            Exit For
        End If
    Next

    Printer.FontName = "Arial"
    Printer.FontSize = 16
    Printer.CurrentX = 20
    Printer.CurrentY = 20

    Printer.Print "novaPDF says Hello World from VB"
    Printer.EndDoc

    ' Return to previous settings
    pNova.SetActiveProfile2 activeProfile, bPublicProfile
    pNova.DeleteProfile2 "Test VB", PROFILE_IS_Public
    Exit Sub
ErrorHandler:
    Debug.Print Err.Number & ":" & Err.Description
End Sub
```

2.4.6.2 VB Converter

The **VB Converter** sample demonstrates how to convert an existing file by printing it to novaPDF Printer using the ShellExecute function. It also demonstrates how to set different options and manage profiles.

The same approach should be taken if you print using a "Print()" method from another object (like an internet browser or a report control). Just replace the ShellExecute call with the call of your Print method.

When the application starts, it creates a few profiles and makes different settings in the profiles. Then it shows a dialog from where the user can select the active profile and change its settings using the controls from the dialog.

After that a document can be selected from the harddisk and printed to novaPDF Printer using the ShellExecute function call.

When using this technique to convert a file to PDF, you have to take care of the fact that ShellExecute prints to the default printer. This function returns immediately and does not wait until the print is finished (it may return before the printing is actually started). Therefore you have to set the default printer to novaPDF Printer before calling ShellExecute (using the SetDefaultPrinter method), register FileSaved message (or any other novaPDF Printer message) to be sure that the print job was started. In this message handler restore the default printer (with the RestoreDefaultPrinter method). This way you made sure that the default printer was restored and your document is printed to novaPDF Printer.

Source code snippets

1. Declare INovaPdfOptions variable

```
'create the NovaPdfOptions object
Public m_NovaOptions As New NovaPdfOptions
```

2. Register novaPDF Printer messages

```
Public wm_Nova_FileSaved As Long
Public wm_Nova_PrintError As Long
```

```

Sub Main()
    ' Registering the messages send by the print in order to listen for them
    wm_Nova_FileSaved = RegisterWindowMessage(MSG_NOVAPDF2_FILESAVED)
    wm_Nova_PrintError = RegisterWindowMessage(MSG_NOVAPDF2_PRINTERROR)
    Form1.Show
End Sub

' Sub that will handle the windows messages
Public Function VB_WindowProc(ByVal hwnd As Long, ByVal wParam As Long, ByVal lParam As Long) As Long
    ' For the registered messages perform specific tasks
    If wParam = wm_Nova_FileSaved Then
        OnNovaPDFFileSaved wParam, lParam
        Exit Function
    End If
    If wParam = wm_Nova_PrintError Then
        OnNovaPDFPrintError wParam, lParam
        Exit Function
    End If

    ' For other messages just send them via normal (old) handling process
    VB_WindowProc = CallWindowProc(oldHandler, hwnd, wParam, lParam)
End Function

```

3. Initialize INovaPdfOptions

```

Private Sub Form_Load()

    On Error GoTo ErrorHandler:
    Dim strProfile As String
    Dim strActiveProfile As String

    ' initialize the NovaPdfOptions object
    ' if you have an application license for novaPDF SDK,
    ' pass both the registration name and the license key to the Initialize() function
    ' m_NovaOptions.Initialize(PRINTER_NAME, '<registration name>', '<license key>')
    m_NovaOptions.Initialize PRINTER_NAME, "", "", ""

    ' sets the value of the windows messages handler to VB_WindowProc and sets the oldHandler
    oldHandler = SetWindowLongApi(Me.hwnd, GWL_WNDPROC, AddressOf VB_WindowProc)

    cmbProfiles.Clear

    ....
    Exit Sub
ErrorHandler:
    Debug.Print err.Number & ":" & err.Description
End Sub

```

4. Set novaPDF Printer Options

```

Private Sub AddSmallSize()
    On Error GoTo ErrorHandler

    m_NovaOptions.AddProfile2 SMALL_SIZE_PROFILE, PROFILE_IS_Public

    ' Set some options to this profile

    ' disable the 'Save PDF file as' prompt
    m_NovaOptions.SetOptionLong2 NOVAPDF_SAVE_PROMPT, False, SMALL_SIZE_PROFILE, PROFILE_IS_Public

```

```

' set generated Pdf files destination folder 'c:\'
m_NovaOptions.SetOptionString2 NOVAPDF_SAVE_FOLDER, "c:\", SMALL_SIZE_PROFILE,
' set output file name
m_NovaOptions.SetOptionString2 NOVAPDF_SAVE_FILE, "PDF Converter small size.pd
' if file exists in the destination folder, append a counter to the end of the
m_NovaOptions.SetOptionLong2 NOVAPDF_SAVE_CONFLICT_STRATEGY, FILE_CONFLICT_STR
' don't detect URLs
m_NovaOptions.SetOptionLong2 NOVAPDF_URL_ANALIZE, False, SMALL_SIZE_PROFILE, P

' Set image compression method to JPEG and quality to 75, possible values are
m_NovaOptions.SetOptionLong2 NOVAPDF_USE_IMAGE_COMPRESSION, True, SMALL_SIZE_P
m_NovaOptions.SetOptionLong2 NOVAPDF_IMAGE_COMPRESSION_METHOD, COMPRESS_METHOD
m_NovaOptions.SetOptionLong2 NOVAPDF_IMAGE_COMPRESSION_LEVEL, 75, SMALL_SIZE_P

' make sure text compression is enabled, and set compression level to 9 maxim
m_NovaOptions.SetOptionLong2 NOVAPDF_USE_Text_COMPRESSION, True, SMALL_SIZE_P
m_NovaOptions.SetOptionLong2 NOVAPDF_Text_COMPRESSION_LEVEL, 9, SMALL_SIZE_PR

' disable unused font embedding
m_NovaOptions.SetOptionLong2 NOVAPDF_EMBED_ALL_FONTS, False, SMALL_SIZE_PROFI
Exit Sub
ErrorHandler:
If err.Number <> NV_PROFILE_EXISTS Then Debug.Print err.Number & ":" & err.Des

End Sub

```

5. Start a Print job

```

Private Sub btnStartPrinting_Click()
.....
m_NovaOptions.SetActiveProfile2 cmbProfiles.Text, PROFILE_IS_Public
m_NovaOptions.SetDefaultPrinter
Dim strToExecute As String
Dim r As Long
m_NovaOptions.RegisterEventWindow Me.hwnd
m_NovaOptions.LicenseShellExecuteFile txtFileToConvert
r = ShellExecute(Me.hwnd, "print", txtFileToConvert, "", "", SW_HIDE)
btnStartPrinting.Enabled = True
Exit Sub
.....
End Sub

```

6. Restore default printer when printing finished

```

Private Sub OnNovaPDFFileSaved(wParam As Long, lParam As Long)
m_NovaOptions.UnRegisterEventWindow
m_NovaOptions.RestoreDefaultPrinter
End Sub

Private Sub OnNovaPDFPrintError(wParam As Long, lParam As Long)
Select Case wParam
Case Error_MSG_TEMP_FILE:
MsgBox "Error saving temporary file on printer server", vbOKOnly, "nova
Case Error_MSG_LIC_INFO:
MsgBox "Error reading license information", vbOKOnly, "novaPDF"
Case Error_MSG_SAVE_PDF:
MsgBox "Error saving PDF file", vbOKOnly, "novaPDF"
Case Error_MSG_JOB_CANCELED:
MsgBox "Print job was canceled", vbOKOnly, "novaPDF"
End Select

```

```

        m_NovaOptions.UnRegisterEventWindow
        m_NovaOptions.RestoreDefaultPrinter
    End Sub

```

2.4.6.3 Word OLE VB

The **Word OLE VB** sample is a simple Windows console application that converts a MS Word document (C:\Test.doc) to PDF using Word OLE automation.

Source code

```

' the novapiLib packages must be added as a COM reference
Const PRINTER_NAME As String = "novaPDF Pro v5"
Const PROFILE_IS_Public As Long = 0

' The main entry point for the application.
Public Sub Main()
    On Error GoTo ErrorHandler:

    ' create the NovaPdfOptions object
    Dim pNova As New NovaPdfOptions

    ' initialize the NovaPdfOptions object
    ' if you have an application license for novaPDF SDK,
    ' pass both the registration name and the license key to the Initialize() func
    ' pNova.Initialize2 PRINTER_NAME, '<registration name>', '<license key>'
    pNova.Initialize2 PRINTER_NAME, "", "", ""
    ' get the active profile ...
    Dim activeProfile As String
    Dim bPublicProfile As Long
    pNova.GetActiveProfile2 activeProfile, bPublicProfile
    ' and make a copy of it
    On Error Resume Next
    pNova.CopyProfile2 activeProfile, "VB Word OLE", PROFILE_IS_Public
    If Err.Number <> 0 Then
        ' ignore profile exists error
        If NV_PROFILE_EXISTS <> Err.Number Then
            Debug.Print "Profile VB Word OLE already exists"
        Else
            Return
        End If
    End If
    On Error GoTo ErrorHandler:
    ' set the copy profile as active profile ...
    pNova.SetActiveProfile2 "VB Word OLE", PROFILE_IS_Public
    ' and set some options
    pNova.SetOptionString2 NOVAPDF_INFO_SUBJECT, "Word OLE document", "", PROFILE_
    ' print word document
    Dim objWord As Object
    Dim objDoc As Object
    pNova.InitializeOLEUsage "Word.Application"
    Set objWord = CreateObject("Word.Application")
    pNova.LicenseOLEServer
    Set objDoc = objWord.Documents.Open("C:\Test.doc", False, True)
    objDoc.PrintOut False
    objDoc.Close False
    objWord.Quit False

    ' Return to previous settings

```

```

    pNova.SetActiveProfile2 activeProfile, bPublicProfile
    pNova.DeleteProfile2 "VB Word OLE", PROFILE_IS_Public
    Exit Sub
ErrorHandler:
    Debug.Print Err.Number & ":" & Err.Description
End Sub

```

2.4.7 VBNet

2.4.7.1 Hello World VBNet

Hello World VBNet sample is a simple Windows console application that prints one page with the "novaPDF says Hello World from VB.Net" text to the novaPDF Printer.

It demonstrates the basic use of the INovaPDFOptions interface. The printing job is made using the package "System.Drawing.Printing"

Basically the sample determines the active profile, makes a copy of it into a profile called "Test VBNet", sets the new profile as active, sets the subject of the generated PDF document, prints a page, and restores original printer settings. The location of the generated document depends on whatever the settings are for the current active profile.

Notice

Because of the specific exception based error handling in .NET, all calls to methods in the INovaPDFOptions interface must be nested within a try-catch block. Consider for example that we want to add a profile called "test", but the profile "test" already exists. Then the call `pNova.AddProfile("test")` will throw an "System.Runtime.InteropServices.COMException". with the `ErrorCode` property set to `NV_PROFILE_EXISTS (0xD5DA0006)`.

Source code

```

Imports System
Imports System.Drawing
Imports System.Drawing.Printing
Imports System.Windows.Forms
' the novapiLib package must be added as a COM reference
Imports novapiLib

Module Module1
    ' <summary>
    ' The main entry point for the application.
    ' </summary>
    Const PRINTER_NAME As String = "novaPDF Pro v5"
    Const PROFILE_NAME As String = "Test VBNet"
    Const PROFILE_IS_Public As Integer = 0
    Const NOVAPDF_INFO_SUBJECT As String = "Document Subject"
    Const NV_PROFILE_EXISTS As Long = -707133434

    Sub Main()
        Try
            ' create the NovaPdfOptions object
            Dim pNova As NovaPdfOptions
            pNova = New NovaPdfOptions
            ' initialize the NovaPdfOptions object
            ' if you have an application license for novaPDF SDK,
            ' pass both the registration name and the license key to the Initialize
            pNova.Initialize(PRINTER_NAME, '<registration name>', '<license key>'

```

```

pNova.Initialize(PRINTER_NAME, "", "", "")
' get the active profile ...
Dim activeProfile As String
Dim nActivePublic As Integer
pNova.GetActiveProfile(activeProfile, nActivePublic)
Try
    ' and make a copy of it
    pNova.CopyProfile(activeProfile, PROFILE_NAME, PROFILE_IS_Public)
Catch e As System.Runtime.InteropServices.COMException
    ' ignore profile exists error
    If (NV_PROFILE_EXISTS = e.ErrorCode) Then
        System.Console.WriteLine("Profile already exists")
    Else
        ' more serious error, propagate it
        Throw e
    End If
End Try
' set the copy profile as active profile ...
pNova.SetActiveProfile(PROFILE_NAME, PROFILE_IS_Public)
' and set some options
pNova.SetOptionString(NOVAPDF_INFO_SUBJECT, "VB.Net Hello document", P
' print a test page, using the previously set active profile
Dim pd As PrintDocument = New PrintDocument
pd.PrinterSettings.PrinterName = PRINTER_NAME
AddHandler pd.PrintPage, AddressOf PrintPageFunction
pd.Print()
pNova.SetActiveProfile(activeProfile, nActivePublic)
pNova.DeleteProfile(PROFILE_NAME, PROFILE_IS_Public)
Catch e As System.Runtime.InteropServices.COMException
    MessageBox.Show(e.Message)
Catch e As Exception
    MessageBox.Show(e.Message)
End Try
End Sub

' and finally the function that actually prints the page
Private Sub PrintPageFunction(ByVal sender As Object, ByVal ev As PrintPageEve
    Dim str As String = "novaPDF says Hello World from VB.Net"
    Dim font As Font = New Font("Arial", 16)
    Dim brush As Brush = New SolidBrush(Color.Black)
    ev.Graphics.DrawString(Str, font, brush, 20.0!, 20.0!)
    ev.HasMorePages = False
End Sub

End Module

```

2.4.7.2 VBNet Converter

The VBNet Converter sample demonstrates how to convert an existing file by printing it to novaPDF Printer using the ShellExecute function. It also demonstrates how to set different options and manage profiles.

The same approach should be taken if you print using a "Print()" method from another object (like an internet browser or a report control). Just replace the ShellExecute call with the call of your Print method.

When the application starts, it creates a few profiles and makes different settings in the profiles. Then it shows a dialog from where the user can select the active profile and change its settings using the controls from the dialog.

After that a document can be selected from the harddisk and printed to novaPDF Printer using the ShellExecute function call.

When using this technique to convert a file to PDF, you have to take care of the fact that ShellExecute prints to the default printer. This function returns immediately and does not wait until the print is finished (it may return before the printing is actually started). Therefore you have to set the default printer to novaPDF Printer before calling ShellExecute (using the SetDefaultPrinter method), wait the process to be started (using WaitForExit()), restore the default printer (with the RestoreDefaultPrinter method). This way you made sure that the default printer was restored and your document is printed to novaPDF Printer.

Source code snippets

1. Declare INovaPdfOptions variable

```
Private mobjNovaOptios As NovaPdfOptionsClass
```

2. Initialize INovaPdfOptions

```
mobjNovaOptios = New NovaPdfOptionsClass
```

```
' initialize the NovaPdfOptions object
' if you have an application license for novaPDF SDK,
' pass both the registration name and the license key to the Initialize() functi
' mobjNovaOptios.Initialize(PRINTER_NAME, '<registration name>', '<license key>')
mobjNovaOptios.Initialize(PRINTER_NAME, "", "", "")
```

```
AddSmallProfile()
```

```
AddFullProfile()
```

3. Set novaPDF Printer Options

```
Try
```

```
mobjNovaOptios.AddProfile2(SMALL_SIZE_PROFILE, PROFILE_IS_Public)
```

```
' Set some options to this profile
```

```
' disable the 'Save PDF file as' prompt
```

```
mobjNovaOptios.SetOptionLong2(NovaOptions.NOVAPDF_SAVE_PROMPT, 1, SMALL_SIZE_P
```

```
' set generated Pdf files destination folder 'c:\'
```

```
mobjNovaOptios.SetOptionString2(NovaOptions.NOVAPDF_SAVE_FOLDER, "c:\", SMALL_
```

```
// .....
```

```
Catch ComException As System.Runtime.InteropServices.COMException
```

```
If ((Not ComException.ErrorCode Xor NovaErrors.NV_PROFILE_EXISTS) Xor -1) = 0
System.Diagnostics.Debug.WriteLine("Profile " & "Small Size Profile" & " exists")
```

```
Else
```

```
MessageBox.Show("Error creating Small Size Profile:" & Microsoft.VisualBasic
```

```
System.Diagnostics.Debug.WriteLine(ComException.Message)
```

```
End If
```

```
End Try
```

4. Start a Print job

```
Private Sub btnStartPrinting_Click(ByVal sender As System.Object, ByVal e As System
```

```
UpdateProfileFromDialog()
```

```
mobjNovaOptios.SetActiveProfile2(CType((cmbProfiles.SelectedItem), String))
```

```
mobjNovaOptios.SetDefaultPrinter()
```

```
mobjNovaOptios.LicenseShellExecuteFile(txtFileToConvert.Text)
```

```
Dim myProcess As Process = New Process
```

```

Try
    myProcess.StartInfo.FileName = txtFileToConvert.Text
    myProcess.StartInfo.Verb = "Print"
    myProcess.StartInfo.CreateNoWindow = True
    myProcess.Start()
Catch ex As Win32Exception
    If ex.NativeErrorCode = Error_FILE_Not_FOUND Then
        Console.WriteLine(ex.Message + ". Check the path and filename")
    Else
        ' Note that if your word processor might generate exceptions
        ' such as this, which are handled first.
        If ex.NativeErrorCode = Error_ACCESS_DENIED Then
            Console.WriteLine(ex.Message + ". You do not have permission to print this")
        End If
    End If
End Try
myProcess.WaitForExit(10000)
myProcess.Close()
mobjNovaOptios.RestoreDefaultPrinter()
End Sub

```

2.4.7.3 Word OLE VBNet

The **Word OLE VBNet** sample is a simple Windows console application that converts a MS Word document (C:\Test.doc) to PDF using Word OLE automation.

Source code

```

Imports System
Imports System.Drawing
Imports System.Drawing.Printing
Imports System.Windows.Forms
' the novapiLib package must be added as a COM reference
Imports novapiLib

Module Module1
    ' <summary>
    ' The main entry point for the application.
    ' </summary>
    Const PRINTER_NAME As String = "novaPDF Pro v5"
    Const PROFILE_NAME As String = "Word OLE VBNet"
    Const PROFILE_IS_Public As Integer = 0
    Const NOVAPDF_INFO_SUBJECT As String = "Document Subject"
    Const NV_PROFILE_EXISTS As Long = -707133434

    Sub Main()
        Try
            ' create the NovaPdfOptions object
            Dim pNova As NovaPdfOptions
            pNova = New NovaPdfOptions
            ' initialize the NovaPdfOptions object
            ' if you have an application license for novaPDF SDK,
            ' pass both the registration name and the license key to the Initialize() fu
            ' pNova.Initialize(PRINTER_NAME, '<registration name>', '<license key>');
            pNova.Initialize(PRINTER_NAME, "", "", "")
            ' get the active profile ...
            Dim activeProfile As String
            Dim nActivePublic As Integer

```



```

pNova.GetActiveProfile(activeProfile, nActivePublic)
Try
    ' and make a copy of it
    pNova.CopyProfile(activeProfile, PROFILE_NAME, PROFILE_IS_Public)
Catch e As System.Runtime.InteropServices.COMException
    ' ignore profile exists error
    If (NV_PROFILE_EXISTS = e.ErrorCode) Then
        System.Console.WriteLine("Profile already exists")
    Else
        ' more serious error, propagate it
        Throw e
    End If
End Try
' set the copy profile as active profile ...
pNova.SetActiveProfile(PROFILE_NAME, PROFILE_IS_Public)
' and set some options
pNova.SetOptionString(NOVAPDF_INFO_SUBJECT, "VB.Net Hello document", PROFILE
' set nova default printer
pNova.SetDefaultPrinter()
' print word document
Dim objWord As Object
Dim objDoc As Object
pNova.InitializeOLEUsage("Word.Application")
objWord = CreateObject("Word.Application")
pNova.LicenseOLEServer()
objDoc = objWord.Documents.Open("C:\Test.doc", False, True)
objDoc.PrintOut(False)
objDoc.Close(False)
objWord.Quit(False)
' restore active profile
pNova.SetActiveProfile(activeProfile, nActivePublic)
pNova.DeleteProfile(PROFILE_NAME, PROFILE_IS_Public)
' restore default printer
pNova.RestoreDefaultPrinter()
Catch e As System.Runtime.InteropServices.COMException
    MessageBox.Show(e.Message)
Catch e As Exception
    MessageBox.Show(e.Message)
End Try
End Sub

End Module

```

2.5 Licensing and Registration

Licensing

novaPDF SDK is fully functional with no time limitation. A notice is printed on each PDF page mentioning the novaPDF Printer.

There are two possibilities for using novaPDF SDK.

Application license

If you buy one application license and register novaPDF SDK, you can integrate novaPDF SDK in one application and you can distribute your application to an unlimited number end users without additional fees. If you develop 2 applications that use novaPDF SDK, you need 2 application licenses.

novaPDF SDK comes with novaPDF Printer Professional. You can also distribute it free of charge.

The notice is removed only when printing from applications that use the novaPDF SDK. If you print from other applications (MS Office, Notepad,...) the notice will still be printed on the bottom of each page.

Evaluation

You can choose not to buy and register novaPDF SDK. You can still distribute novaPDF SDK and novaPDF Printer, but then the notice will be printed on each page of the PDFs created from your application that integrates novaPDF SDK.

If your end users want the notice to be removed they will have to register an edition of novaPDF Printer on each computer where they use your application. Depending on the features of the novaPDF SDK integrated in your application, your clients will have to register Lite, Standard or Professional edition of novaPDF Printer. For example if you integrate features available only in novaPDF Printer Pro in your application, your end users will benefit of these features only if they register novaPDF Printer Pro.

Once your end users register an edition of novaPDF Printer, they will be able to generate PDF files, without the notice, from any application.

Registration

There is no window where you can enter a key and register novaPDF SDK.

The purpose of the registration key you receive after purchase is to remove the notice that appears on each PDF page. For this you have to pass the registration key to the Initialize method of INovaPdfOptions interface, each time you call it. Please make sure you use the correct key that you received after purchase.

If you lost your registration key, please send us your purchase information (purchase number and approximate date), specify the name (company name) and email address you used to buy your copy of novaPDF Printer. We will send you the registration key again.

Index

- A -

Addbookmarkdefinition 55
Addbookmarkdefinition2 56
Addpredefinedform 45
Addpredefinedform2 45
Addprofile 38
Addprofile2 38
AddWatermarkImage 66
AddWatermarkImage2 68
AddWatermarkText 80
AddWatermarkText2 82

- C -

Choose sample 94
Components 9
Copyprofile 39
Copyprofile2 39
CSharp converter 106

- D -

Deletebookmarkdefinition 60
Deletebookmarkdefinition2 60
Deleteprofile 41
Deleteprofile2 41
DeleteWatermarkImage 74
DeleteWatermarkImage2 74
DeleteWatermarkText 87
DeleteWatermarkText2 87
Distribute 12

- E -

Enablebookmarkdefinition 61
Enablebookmarkdefinition2 62
EnableWatermarkImage 74
EnableWatermarkImage2 75
EnableWatermarkText 88
EnableWatermarkText2 88

- G -

Getactiveprofile 43
Getactiveprofile2 44
Getbookmarkdefinition 62
Getbookmarkdefinition2 63
Getbookmarkdefinitioncount 65
Getbookmarkdefinitioncount2 66
Getbookmarkheadercount 64
Getbookmarkheadercount2 65
Getfirstform 49
Getfirstform2 50
Getfirstprofile 41
Getfirstprofile2 42
Getnextform 51
Getnextform2 51
Getnextprofile 42
Getnextprofile2 43
Getoptionencstring 32
Getoptionencstring2 32
Getoptionlong 36
Getoptionlong2 36
Getoptionstring 30
Getoptionstring2 31
Getpdffilename 93
Getpredefinedform 46
Getpredefinedform2 47
GetWatermarkImage 75
GetWatermarkImage2 77
GetWatermarkImageCount 79
GetWatermarkImageCount2 79
GetWatermarkText 89
GetWatermarkText2 91
GetWatermarkTextCount 92
GetWatermarkTextCount2 93

- H -

Hello World 110
Hello World CSharp 104
Hello World Delphi 100
Hello World VB 120
Hellow World network 113
Hellow World VNet 125

- I -

Initialize 28
 Initialize2 29
 Initializeoleusage 54
 InitializeSilent 29
 InitializeSilent2 30
 INovaPdfOptions 26
 Installation 9
 Integrate 11
 Introduction 7

- L -

Language codes 14
 LicenseApplication 55
 Licenseoleserver 54
 Licenseshellexecute file 54

- M -

Make the release build 12
 MFC Converter 115
 MFC Scribble 118
 Modifybookmarkdefinition 57
 Modifybookmarkdefinition2 59
 ModifyWatermarkImage 70
 ModifyWatermarkImage2 72
 ModifyWatermarkText 83
 ModifyWatermarkText2 85

- N -

Network auto-install 10

- P -

PDF reports 95
 Private/Public Profiles 17
 Purchasing and Registration 129

- R -

Register COM 15
 Register messages 17

Registereventwindow 53
 RegisterNovaEvent 53
 RegisterNovaEvent2 53
 Registry Keys 18
 Removepredefinedform 47
 Removepredefinedform2 48
 Renameprofile 40
 Renameprofile2 40
 Restoredefaultprinter 52

- S -

Set printer options 16
 Setactiveprofile 44
 Setactiveprofile2 44
 Setdefaultprinter 52
 Setformvisible 48
 Setformvisible2 49
 Setoptionencstring 34
 Setoptionencstring2 35
 Setoptionlong 37
 Setoptionlong2 37
 Setoptionstring 33
 Setoptionstring2 34
 Silent Installer 12
 System requirements 9

- U -

Unregistereventwindow 53
 Use COM 15
 Use Events 18

- V -

VB converter 121
 VCL converter 96

- W -

WaitForNovaEvent 54
 Windows messages 25
 Word OLE CSharp 108
 Word OLE Delphi 102
 Word OLE VB 124